

# Signal Integrity





# Copyrights

Software, documentation and related materials: Copyright © 2002 Altium Limited

This software product is copyrighted and all rights are reserved. The distribution and sale of this product are intended for the use of the original purchaser only per the terms of the License Agreement.

This document may not, in whole or part, be copied, photocopied, reproduced, translated, reduced or transferred to any electronic medium or machine-readable form without prior consent in writing from Altium Limited.

U.S. Government use, duplication or disclosure is subject to RESTRICTED RIGHTS under applicable government regulations pertaining to trade secret, commercial computer software developed at private expense, including FAR 227-14 subparagraph (g)(3)(i), Alternative III and DFAR 252.227-7013 subparagraph (c)(1)(ii).

P-CAD is a registered trademark and P-CAD Schematic, P-CAD Relay, P-CAD PCB, P-CAD ProRoute, P-CAD QuickRoute, P-CAD InterRoute, P-CAD InterRoute Gold, P-CAD Library Manager, P-CAD Library Executive, P-CAD Document Toolbox, P-CAD InterPlace, P-CAD Parametric Constraint Solver, P-CAD Signal Integrity, P-CAD Shape-Based Autorouter, P-CAD DesignFlow, P-CAD ViewCenter, Master Designer and Associate Designer are trademarks of Altium Limited. Other brand names are trademarks of their respective companies.

Altium Limited www.altium.com

# **Table of Contents**

chapter 1	Introduction to P-CAD Signal Integrity	
	P-CAD Signal Integrity Simulator	1
	About this Guide	
	Signal Integrity Features	2
	Features	
	Software I/O Buffer Modeling	2
	User Interface	
chapter 2	P-CAD Signal Integrity - Getting Started	
	System Requirements	5
	Recommended System	
	Minimum System	5
	Installing P-CAD Products	6
	P-CAD Signal Integrity Interface	6
	Accessing P-CAD Signal Integrity	6
	Menu Bar	7
	Toolbar	7
chapter 3	P-CAD Signal Integrity Tutorial	
	Starting up P-CAD Signal Integrity	10
	Import list of PCB nets to analyze	
	Review and Complete your PCB Design Parameters	
	Edit Components	
	Edit Nets	
	Edit Layer Stack	13
	Select nets to Analyze	15
	Select Nets by Net Class	
	Edit Components specifications	17
	Screen the Nets	
	Run Reflection Simulation	26
	Run Crosstalk simulation	33
	Create a Macromodel	
	Create a new Macromodel from an IBIS file	39
chapter 4	P-CAD Signal Integrity Command Reference	

	File Commands	
	File Open	43
	File Get Nets	44
	File Reports	44
	File SULTAN Out	
	File Exit	
	Edit Commands	
	Edit Take Over	_
	Edit Get PCB Selected Nets	
	Edit Find Coupled Nets	
	Edit Layer Stack	
	Edit Components	
	Edit Nets	
	Luit NGIS	
chapter 5	P-CAD Signal Integrity Screening Commands	
chapter 5		
	File Commands	
	File Report	57
	File SDF Out	61
	File Close	62
	Edit Commands	62
	Edit Delete	62
	Edit Select All	62
	Edit Invert Selection	62
	View Commands	
	Net Data View	
	Impedance View	
	Voltage View	
	Timing View	
	Arrange Nets	
	Select Columns	
	Help Commands	
	Help Topics	
	About Help	07
shantar 6	D CAD Signal Integrity Simulation Commands	
chapter 6	P-CAD Signal Integrity Simulation Commands	
	Termination Advisor	69
	Set Victim Net	75
	Set Aggressor Net	75
	Reflection	75
	Crosstalk	76
chapter 7	P-CAD Signal Integrity Wave Analyzer	
		70
	Wave Analyzer File Commands	
	File Open	
	File Save	
	File Save As	
	File Print	79

	File Page Setup	
	File Exit	-
	Edit Commands	-
	Edit Copy	
	Edit Rescale	
	Edit Redraw	-
	Edit Delete Selected Wave	82
	Edit Delete all Waves	82
	Edit Clear Measurement Area	82
	Edit Zoom In	82
	Edit Zoom Out	83
	Edit Origin	
	Analyze Commands	
	Analyze Cartes	83
	Analyze FFT	84
	Analyze Rise Time	85
	Analyze Fall Time	85
	Analyze Minimum	85
	Analyze Maximum	86
	Analyze Baseline	86
	Analyze Topline	
	Options Commands	87
	Options Measurement Area	
	Options Wave Names	
	Options Display	
	Options Coordinate System	
	Options X-Axis	
	Options Y-Axis	
	Options Wave	90
	Help Commands	90
	WaveAnalyser Help Topics	
	How to Use Help	
	About WaveAnalyzer	
	•	
chapter 8	General Commands	
	Library Commands	93
	Macromodel Editor	
	Description of the library tree	94
	IC Models	
	IC Input, IC Tristate	
	IC Output Models	98
	Resistors, Inductors, Capacitors Models	100
	Diode Models	102
	BJT Transistor	104
	Connector (Transmission line)	108
	Connector (Lumped Element)	
	File Commands	
	File Exit	

	Edit Commands	109
	Edit Open	109
	Edit Add	
	Edit Save	110
	Edit Save As	110
	Edit Close	
	Edit Delete	
	Window Commands	110
	Window Cascade	
	Window Arrange Icons	111
	Window Next	
	Import IBIS File	
	IBÍS File	
	File Open	112
	Export	
	Report	
	Exit	
	Options Commands	
	Configure	
	Simulator	
	Help Commands	119
	Signal Integrity Help Topics	119
	How to use Help	119
	About P-CAD Signal Integrity	119
nnondiy A	List of Signal Integrity Digital Integrated Circuita	
appendix A	List of Signal Integrity Digital Integrated Circuits	
	Signal Integrity Device Library	
	Signal Integrity Device Handling/Search	
	Digital Integrated Circuits included in P-CAD Signal Integrity	122
annendix R	List of Signal Integrity System Messages	
Appondix =		400
	Signal Integrity System Messages	
	Wave Analyzer Messages List	
	P-CAD IBIS Converter System Messages	171
appendix C	Units and Default Values	
	Units Representation	173
	Common Unit Factor Characters	
	Common Units	
	Editor Parameter Descriptions	

# **Introduction to P-CAD Signal Integrity**

Congratulations on your purchase of a high performance simulator to complement your copy of P-CAD PCB. The applications are paired for fast simulation of reflection effects and are seamlessly integrated for your ease of use.

Two simulation products are documented in this manual:

- P-CAD Signal Integrity Reflection Simulator
- P-CAD XTalk Crosstalk Simulator

The menu structure and user interface is consistent for all P-CAD products. Options specific to each particular simulation are offered through context-sensitive dialogs, giving you exactly those options supported by your simulator, but in a familiar environment.

# P-CAD Signal Integrity Simulator

When you choose the P-CAD Signal Integrity Simulator its entry screen appears. It lets you select PCB nets to analyze from your P-CAD PCB database or from SULTAN files. It loads these in the simulator, display their details and enables interactive modification of parameters. When parameters are missing, default parameters are used. These are listed in the section discussing the parameters. P-CAD Signal Integrity also provides access to start and restart the simulation process.

## **About this Guide**

This manual includes information on the use and operation of the following products:

- P-CAD Signal Integrity
- P-CAD Xtalk

The information in this manual is presented in tutorial and reference format. It is designed to get you started simulating, and to present some advanced features which will be helpful as you gain more experience of the functionality of the simulators.

# Signal Integrity Features

As Windows based PCB design tools become more and more sophisticated and are used to design printed circuit boards with high clock speeds and high density, the demand for simulation tools addressing signal integrity problems has increased dramatically.

P-CAD Signal Integrity has been created specially for PCB designers using the P-CAD PCB tool, and is tightly coupled to the PCB to provide a simple interactive simulation environment. Using P-CAD Signal Integrity, design engineers may check their multilayer boards for noise effects like ringing and crosstalk. When installed, P-CAD Signal Integrity is seamlessly integrated with P-CAD PCB, giving you the familiarity of P-CAD PCB's Windows™ interface standard and easy access to its powerful capabilities.

P-CAD Signal Integrity is based on a Fast Reflection and Crosstalk Simulator, which produces very accurate simulations, (provided that full model information is available), with algorithms proven in industry.

The P-CAD Signal Integrity simulator uses the characteristic impedance of the traces calculated through a transmission line calculator and I/O buffer macro-model information as input for the simulations. Where model information is not available the system utilizes fallback models.

#### **Features**

- Provides fast simulation of reflection and crosstalk effects.
- Fast screening (pre-analysis) for signal integrity effects (over- and undershoot, delay, etc.) for entire boards with spreadsheet-like result display.
- Seamlessly integrated with P-CAD PCB, allowing access to simulation options.
- No special expertise is required to use it, due to the simple user interface and tight integration.
- As the system utilizes I/O buffer macro-models, no knowledge of SPICE or analogue simulation is required.
- Oscilloscope type display of simulation results with integrated result measurement facilities.
- Well-proven algorithms for the calculation of the transmission line characteristics and subsequent simulations.
- What-if-analysis concerning different termination strategies with parametric values of resistors/capacitors and through easy substitution of macro-models.
- What-if-analysis concerning different routing strategies through tight integration with P-CAD PCB.

## Software I/O Buffer Modeling

- Macro-model approach for fast and accurate simulation.
- Supplied with a basic IC model library including verified models.
- Automatic model attachment according to Part Number.

- Supporting the IBIS 3 industry standard sub-set for I/O buffer modeling.
- Integrated macro-model-editor allows easy and fast definition of own models using databook or measurement values.
- P-CAD Signal Integrity utilizes the P-CAD PCB, DBX API interface for interactive communications.
- P-CAD Signal Integrity can be loaded with complete PCBs or subsets of data (single or multiple nets, single layers, etc.).
- P-CAD Signal Integrity supports cross highlighting with the layout (nets under analysis).
- P-CAD Signal Integrity can provide an INCASES EMC-WORKBENCH 'SULTAN" file for extended EMC analysis.
- P-CAD Signal Integrity can back annotate termination networks onto the board as a DRC marker.
- P-CAD Signal Integrity and Xtalk are designed for analyzing PCB's with consistent power and/or
  ground planes. Use of the tools on boards without consistent power or ground planes will lead
  to untrustworthy results.

#### **User Interface**

There are three basic operational screens for P-CAD Signal Integrity: the net screen, the preanalysis screen and the result screen. The net screen and the result screen can be utilized simultaneously.

# P-CAD Signal Integrity - Getting Started

This chapter gives information on the required hardware and software needed before installing P-CAD Signal Integrity products. It also introduces you to the P-CAD Signal Integrity interface.

# **System Requirements**

Make sure that your PC and its software conform to the following P-CAD requirements and recommendations.

## **Recommended System**

- Windows NT 4/2000 Professional
- PC with Pentium III Processor
- 128MB RAM (256MB for high component/net count)
- 400MB Hard Disk Space
- Desktop area 1024x768 pixels
- 32-bit Color Palette
- CD-ROM Drive
- Mouse or compatible pointing device

## Minimum System

- Windows 95/98/2000Me
- PC with Pentium 166MHz
- 64MB RAM
- 200MB Hard Disk Space (without ISO libraries)
- Desktop area 800x600 pixels

- 256 Color Palette
- CD-ROM Drive
- Mouse.

# **Installing P-CAD Products**


For up-to-date installation information refer to the file Readme.WRI, located on the product CD. This file can also be found in the application program folder (\Program Files\P-CAD 2002) after installation. Note that the setup program on the Product CD can also be used to repair or remove an existing P-CAD Installation.

# P-CAD Signal Integrity Interface

You are probably already familiar with the P-CAD PCB interface in addition to being proficient in the operation of Windows, so every detail of the screen is not provided here.

# Accessing P-CAD Signal Integrity

P-CAD Signal Integrity simulator is accessed by choosing **Utils » P-CAD Signal Integrity** from the P-CAD PCB menus. This brings up the simulator entry window. You can now choose PCB nets and analyze them using either commands from the pull-down menu or icons on the tool bar.



#### Menu Bar



P-CAD Signal Integrity menu bar, displayed on the simulator entry screen, provide access to commands that let you:

- Bring in PCB nets to analyze
- Review/complete/modify PCB design parameters
- Launch simulations
- Produce reports
- Create output files
- Import IBIS files and create Macromodels
- Specify simulator options and preference settings.


#### Toolbar



The toolbar consists of graphical display buttons (icons) that correspond to commonly used P-CAD Signal Integrity commands. These icons appear just below the menu bar on the P-CAD Signal Integrity entry screen.

Tool Tips explain each of the toolbar buttons. To activate a Tool Tip, place the mouse over the button. The Tool Tip pops up.

The icon display is context sensitive, so icons not highlighted indicate commands not available at this stage. The commands linked with each icon are listed below:



	Take Over Selected Nets
<b>₽</b>	Start the Termination Advisor
	Start Net Screening
	Start Reflection Simulation
4	Set Victim Net
9	Set Aggressor Net
<b>]</b>	Start Crosstalk Simulation

The simulation commands Reflection and Crosstalk give access to the Wave Analyzer, which has its own icons and menu bar.

# **P-CAD Signal Integrity Tutorial**

This tutorial includes hands-on instructions to help you become familiar with how to use P-CAD Signal Integrity to analyze and simulate your PCB designs and to investigate remedies to signal integrity problems.

The following steps indicate what you will accomplish in this tutorial.

- 1. Starting up P-CAD Signal Integrity
  - Import list of PCB nets to analyze
- 2. Review and complete your PCB design parameters
  - Edit Designator specifications
  - Edit Supply Nets specifications
  - Edit Layer Stack specifications
  - Select nets to analyze
  - Edit Components specifications
- Screen the Nets
- 4. Run Reflection simulation
  - Modify parameters
  - Re-run simulation
  - Produce a report
- 5. Run Crosstalk simulation
  - Modify parameters
  - Re-run Crosstalk simulation

- Produce a report
- 6. Create a Macro Model
  - Edit Macro Model
  - Create a new Macro Model from an IBIS file
- 7. Specify simulation options and preference settings.

Each of these steps is discussed in detail in this tutorial. It will be worth your time to go through the complete tutorial, which is designed to get you going quickly.

If a message is displayed by the system during the tutorial, see *Appendix B - System Messages*, for a description of the problem and a possible solution.


For more detailed information about any of the commands and options used in this tutorial, refer to the relevant *Commands Reference* chapters.

Please note that the examples do not reflect the current state of the art techniques to avoid and solve signal integrity problems. The Termination methods used in the different examples are for tutorial purposes only.

# Starting up P-CAD Signal Integrity

In this tutorial we will analyze nets from the demo PCB provided with P-CAD Signal Integrity. Within P-CAD PCB, open the file \P-CAD 2002\Demo\Signal Integrity\demo.pcb.

Start the Signal Integrity program by choosing **Utils » P-CAD Signal Integrity** from the P-CAD PCB menus. This will display the Signal Integrity entry window.




The toolbar display is context sensitive, and only commands available at each stage have their icon highlighted.

## Import list of PCB nets to analyze



The first step is to import the nets from the PCB into P-CAD Signal Integrity. To do this click on the **Get Netlist** icon, or choose **File** in the menu bar and select **Get Nets** from the pull-down menu.

This will list, on the left of the window in the All Nets column, all the nets in the PCB currently open in P-CAD PCB.




## Review and Complete your PCB Design Parameters

We can now edit and modify:

- The electrical component types
- 2. The supply nets
- 3. The Layer Stack of the whole PCB
- 4. The choice of nets to analyze
- The components specifications.

## **Edit Components**

To access the Edit Components dialog, choose **Edit** in the Menu bar and select **Components** from the pull-down menu. The Components list box contains the names of all components in the active design. You can select individual or multiple components in the list box. Once selected you can specify the electrical type of a component.



Select the component **C1** in the **Component** list. Note that the Category is already set to Capacitor. If it was not, you would choose the type **Capacitor** in the Category drop down list. Confirm that all other capacitors have their Category set to **Capacitor**.

In the same way confirm that the components **D1** and **D2** are set to **Diode**, **J1** is set to **Connector**, **R1**, **R2** and **R3** are set to **Resistor**, and **U1** to **U9** are set to **IC**.

With the button **To Database** you can save the specified component type back to the PCB currently open in P-CAD PCB. The information is saved in the PCB as a component attribute.

A second way to specify the component type is to define a component attribute directly in P-CAD PCB. Define the Component attribute Category, and set the value of the attribute to one of the following qualifiers. If you now load the design into P-CAD Signal Integrity, the components will have their Category already defined (as in the demo file).

The following electrical component types are supported:


Component Type	Attribute Value
Bipolar Junction Transistor	BJT
Capacitor	Capacitor, Cap
Connector	Connector, Con
Diode	Diode, Dio
IC	IC
Inductor	Inductor, Ind
Resistor	Resistor, Res

If you do not set the Category, P-CAD Signal Integrity will use the type IC.

#### **Edit Nets**

Although Supply Nets can not be simulated, they are necessary for the correct simulation of nets with Pull-up or Pull-down components.

To access the *Edit Nets* dialog, click on **Edit** on the Menu bar and choose **Nets** from the pull-down menu.



The *Edit Nets* dialog contains the names of all nets in the active design. You can select individual or multiple nets in the list box. Once selected you can specify the category and the voltage of the net.

Select the net **VCC** in the net list box, choose the category **Supply** in the Category drop down list, enter **5V** as the Value and click the **Apply** button for the changes to take place. In the same way set the category **Supply** and the value **5V** for the nets **VCC**, **VCC1**, **VCC2** and **VCC3**.

With the button **To Database** you can save the specified net category and value to your P-CAD PCB. The information is saved in the PCB as net attributes.

A second way to specify the net category and value is to define net attributes directly in P-CAD PCB. Define the net attribute Category and set the value of the attribute to **Supply**, and the net attribute Voltage and set the value to the voltage of the net. If you now load the design into P-CAD Signal Integrity, the nets get the defined category and value.

## Edit Layer Stack

For the calculation of the correct electrical behavior of the traces, the layer stack of the PCB must be specified.

The required parameter definitions and their applicable default values are listed below:


Parameter definition	Defaults
The correct sequence of the layers	None
The thickness of the different copper	35μm
and dielectric planes	0.32mm
The dielectric constant of the substrate	$\varepsilon \tau = 4.8$

The layer stack and all associated transmission line parameters are automatically saved in a layer stack information file. The file is named as the same as the PCB, with the extension .TDB. It is saved into a folder with the same name as the PCB, under the Projects folder. For example, for the demo board it is \P-CAD 2002\Projects\Demo\Demo.tdb.

Before a new transmission line parameter is calculated, the system checks if appropriate transmission line parameters already exist in the database file.

Whenever the layer stack is changed, the old database file gets deleted and a new one is generated.

Choose **Edit** on the Menu bar and select **Layer Stack** from the pull-down menu to access the Layer Stack Specifications window. The signal and plane layers are displayed in the *Layer Stack* dialog.



This window shows the layer name, the layer type (Signal or Plane), and the layer number as defined by the user in P-CAD PCB. Here you can modify the Dielectric and Copper property definitions for a layer. To do so select a layer and enter the changes required in the available entry windows.


When you enter the Copper thickness and the Dielectric value, the Dielectric referred to is the one immediately above the Copper layer. As a result, it is not possible to enter a Dielectric value for the top layer.

All the layers except the Top and Bottom layers can be moved up or down, by selecting a layer and clicking the appropriate button. The Top layer is always number 1, and the Bottom layer which is always number 2 and at the bottom.

For the purpose of this tutorial, we will leave the layer stack unchanged. Click **OK** or **Cancel** to close the window.

## Select nets to Analyze


In the Signal Integrity main entry dialog, choose the nets DEMO\_D0 to DEMO\_D31, by clicking and holding the left mouse button on DEMO\_D0 and dragging the cursor to select all DEMO\_Dx nets. This will highlight the desired nets.



To analyze these nets, the simulator must acquire all the required data for simulation. The editor does this when you do one of the following:



- Click on the Takeover icon or
- Choose **Edit** in the menu bar and select **Take Over** from the pull-down menu. The simulator acquires the nets' data and displays the details in the simulation windows.



The selected nets are listed in the top window on the right hand side.

For each selected net, the following are displayed:

- The Net name (some net names are concatenated).
- The Net length (the sum of the length of all trace segments).
- The Net characteristic impedance (the average impedance derived by the sum of the impedance of each trace segment multiplied by the length of the trace segment and divided by the sum of the length of the traces).

The bottom right hand window displays the connected pins for the net selected in the top simulation window.

Scroll down and select <code>DEMO\_D5\_DEMO\_NET11</code> from the top simulation window.

## **Select Nets by Net Class**


Allows you to analyze nets by net classes. Normally, the left list box shows the names of all nets of the current design. To analyze only a group of nets, define net classes in P-CAD PCB and assign the affected nets to the class. After pressing the button **Get PCB Nets**, the drop down list **Net Class** is filled with all net classes of the design.

Select a net class and the list below contains only the nets of that class. To see all nets, select the entry **All**.

### **Edit Components specifications**


The Edit Buffer button, located on the Signal Integrity entry window, gives access to the component's data dialog. We will look at data windows for IC's, Resistors and Capacitors. Other components will display different screens as applicable.

First, on the Signal Integrity bottom right-hand window, select the component: U1.



Use the **In <-> Out** button to modify the direction specification for the selected component, to change it from the input to output or vice versa. Return the buffer to an Output.

To modify the specifications for components, click on the **Edit Buffer** button. This displays the *Integrated Circuit* dialog. You can change the Model data and the Stimulus used by the simulator for the highlighted components, in our case U1.



The **Model** tab shows the current settings for the IC component selected. Choosing a Technology and Direction will automatically give a list of input and / or output models as appropriate. For the purpose of this tutorial, we will leave the Model settings unchanged.

Changes to technology and direction are used locally in the design. If however, you wish to update the library to reflect changes, then click on **Save to Library** button. Remember that you are modifying the library when you do this, so care should be taken to ensure that the library is not corrupted for future use.


Choose the Stimulus tab. In the Stimulus window you can modify the Stimulus which is applied to the input of the output I/O buffer for Simulation to:

Constant Level,

Single Pulse or

Periodic Pulses.

Select the **Single Pulse** or **Periodic Pulse** option in the Stimulus Type box, and notice that you can set the Start Level to High or Low in the Start Level box. The wave display will change to reflect your choices.



You can also specify Start and Stop times of the pulse and the Period time if a periodic pulse is chosen.

Stimulus details can be saved to a file. This is described in the *Edit* section of *the Command Reference* chapter.



Stimulus details may also be loaded from a file. To do so, click the **Load** button. The *Load Stimulus* dialog is displayed. Choose the demo stimulus file, single.stm, located in the stimuli subdirectory and click the **Open** button. This will update the **Stimulus** tab with the details of the file.

Click **OK** to close the *Integrated Circuit* dialog.


Back in the Signal Integrity window, select component 'R2'.

Resistor Component Designator: R2 Part: RES400 Pin 1 Pin 2 Value Pin 1: ▼ Add 2 • Pin 2: Remove Value: 68 Ohm ÖK Cancel

Now click the **Edit Buffer** button again. This displays the *Resistor* dialog.

You can add or remove pins for connections routed to resistor arrays. For the purpose of this tutorial, we will make no change to this resistor. Click the **Cancel** button to close the *Resistor* dialog.

Back in the Signal Integrity window, select the component C1 and choose the **Edit Buffer** button to display the *Capacitor* dialog.



Again, leave the Capacitor unchanged, and click the **Cancel** button.

## **Screen the Nets**


Screening provides a fast simulation of many nets to enable you to get closer information about the nets and to identify critical nets for closer examination. Besides geometrical information, it also provides estimated values for Signal Integrity effects (overshoot, undershoot).

When screening bi-directional nets, both directions are simulated and the worst result of each effect is displayed.

The Screening commands can be accessed from the Simulation pull-down menu or by clicking the Screening icon.



Click on the **Screening** icon to get the Screening window to display details for the currently selected nets.



The data displayed when you enter the Screening window shows the information requested on the last access. We will review each of the screening views and identify nets to analyze in greater detail.

The message in the comment window indicates that nets with Diodes or Transistors cannot be analyzed by the Screening fast simulation method. These can, however be simulated using the Reflection and Crosstalk simulation options.

First, click on all of the four results display icons, which are currently highlighted, to switch the options off.






Click on the **Net Data View** icon. This displays for each net:

- The net name
- The length of the trace
- The number of components connected to the traces
- The number of segments in each trace.


Now click on the **Net Data View** icon again to switch this view off.





Next, click on the **Impedance View** icon. This displays for each net:

- The net name
- The average impedance of the whole trace
- The minimum impedance of the whole trace
- The maximum impedance of the whole trace.



Click on the **Impedance View** icon again to switch this view off.




Now, click the **Voltage View** icon, and drag the right edge of the Screening window to enlarge it and display more columns on the screen.

To display all the seven columns at once, you can make the columns narrower by clicking a column edge on the header line and dragging the column to the desired width.

This displays for each net:

- The net name
- The Top Voltage Value for the Rising Edge
- The Maximum Overshoot for the Rising Edge
- The Maximum Undershoot for the Rising Edge
- The Base Voltage Value for the Falling Edge
- The Maximum Overshoot for the Falling Edge
- The Maximum Undershoot for the Falling Edge.




You can select to display only the columns of interest on a view, to ease the identification of problem nets by defined criteria.

Let's view the Maximum Overshoot (Rising Edge) and Maximum Undershoot (Falling Edge).

Choose the View command on the screening header menu.

Select the **Select Columns** command.

In the *Select Columns* dialog, click the **Voltage** tab. On the Voltage tab, choose to display only the Maximum Overshoot on the Rising Edge and Maximum Undershoot on the Falling Edge, by disabling all other options as displayed below. Click **OK**.




This will now display only the two chosen columns on the Voltage View.

We can also sort the nets by values within displayed columns.

From the **View** menu, select the **Arrange Nets By** command. The **Arrange Nets By** menu is displayed highlighting only the columns currently displayed.

Select **Maximum Overshoot** (**Rising Edge**). This displays the nets sorted in order of Maximum Overshoot.




Now click on the **Voltage View** icon again to switch this view off.



Lastly, click on the **Timing View** icon. This displays for each net:

- The net name
- The Slope for the Rising Edge
- The Flight Time for the Rising Edge
- The Slope for the Falling Edge
- The Flight Time for the Falling Edge.




You can identify the nets displaying the longest flight time.

Now close the screening window using the **X** in the top right corner.

### **Run Reflection Simulation**



Back on the Signal Integrity main screen, select the net DEMO\_A31 in the All Nets column. Click the **Takeover** icon to acquire data for this net.



The Reflection simulator calculates voltages at nodes of a net using routing and layer information of the PCB and associated driver and receiver I/O buffer models.

A 2D-field solver automatically calculates the electrical characterization of the lines. Modeling assumes that DC path losses are small enough to be ignored. The simulator provides you with detailed and highly accurate information on all signal integrity related aspects, such as overshoot, undershoot and timing. The results are presented in an oscilloscope-like wave analyzer.



To start a Reflection simulation, you can either click on the **Reflection Simulation** icon, or choose **Simulation** in the menu bar and select **Reflection** from the pull-down menu.

The simulator runs a reflection simulation on the nets displayed in the simulation window.

The results of the Reflection simulation are returned on the WaveAnalyzer screen.

The X and Y specified on the bar under the WaveAnalyzer screen indicate the location of the cursor on the display.


The display above shows the wave U9.9 (U9, pin 9 on net DEMO\_A31) and wave U1.118 (U1, pin 118 on net DEMO\_A31) as the worst for overshoot and undershoot. Let's look at the range of the overshoot for each of these waves.

Select the wave U9.9 by clicking on the line beneath its name which is displayed on the right of the wave display.

The WaveAnalyzer Analyze commands allow you to display the simulation results as waveform measurements. Click on the Minimum, Maximum, Base Line, Top Line icons.




The calculated measurements are displayed in the Measurements area of the WaveAnalyzer window. These measurements can also be performed using the pull-down options of the **Analyze** menu.





Let's zoom in on the worst overshoot area on the top left of the display. To do so, click the **Zoom In** icon then click and hold the mouse button on the top left corner, then drag the cursor toward the bottom right to define the zoom region. The picture below displays the zoomed area with its measurements.



Clear the measurement area by selecting **Clear Measurement Area** on the **Edit** pull-down menu. Now reselect Minimum, Maximum, Baseline and Topline.

The measurements are display dependent. The measurements displayed are for the selected wave within the currently visible area. If you compare the measurements of the zoomed graph with the measurements of the original chart, you can see that the measurement values are different. They now show the measurements for the currently displayed waveforms.

To return the display to the original full waves display, select the **Origin** command from the **Edit** pull-down menu.


Let's save the current wave as DEMO\_A31 for subsequent reference.

Do this by selecting **Save As** on the **File** pull-down menu.

The File Save dialog is displayed. Here you can specify the directory and filename for the wave file you want to save.

Enter DEMO A31 in the File Name field and click the Save button.

When saving using the File Save command, the default name result.dia is given. This default can be changed, by entering a new name, as appropriate. The current file name, displayed on the title bar, is overwritten each time the File Save command is issued.



Close the Waveform Analyzer by clicking the **X** in the upper right corner. The file saved can later be opened using the **File Open** command.

Having identified the net DEMO\_A31 as problematic, let's go back to the Signal Integrity screen to select it and try a termination on the component U9 pin 9 to reduce the overshoot.




To do so, we first select the entry U9 pin 9 in the Signal Integrity window. Click on the **Termination Advisor** icon.

The Termination examples given here are for the purpose of demonstrating the tool only and may not be appropriate in the electrical sense.


The Termination Advisor dialog is displayed.

Choose Parallel C to GND termination method and click OK.






Now let's run the reflection simulation again. Click on the **Reflection** icon and on the WaveAnalyzer display, select the wave U9 pin 9 again by clicking on the line under its name and click the measurement icons to display the measurements in the Measurements area.



The overshoot Vmax = 7.11 V, is a slight reduction on the original 7.92 V before the termination was added, but it is still significant. Let's try a different termination.




Close the WaveAnalyzer window and go back to the Signal Integrity window, click on the **Termination Advisor** icon again. This time, select the **Parallel R to GND** Termination with 100 Ohm resistance and click **OK**.






Now let's run the reflection simulation again. Click on the **Reflection** icon. Again, on the WaveAnalyzer display, select the wave U9.9 and click on the measurement icons.






Now let's print out these results.

Select **Page Setup** on the WaveAnalyzer **File** pull-down menu. This displays the *Page Setup* dialog, on which you can specify paper size, source, orientation and margins.



Click on the **Printer** button to specify the printer. On the displayed dialog you can select a printer and enter the property details for the chosen printer.



Click **OK** to accept the printer selection and again to close the *Page Setup* dialog. Then click on **Print** on the WaveAnalyzer **File** pull-down menu. This displays the standard Windows print dialog, and sends the Wave display to the printer.



You can also use the **Print** icon to print the display, when the page setup and the printer details are already specified.


The introduction of the termination appears to have resolved the ringing noise problem.

You can save this termination solution and send it as a DRC error indicator to the P-CAD PCB database. First close the WaveAnalyzer window. Return to the Signal Integrity window.




Click on the **Termination Advisor** icon. Click on the **Send to P-CAD PCB** button and click **OK**.

To display the DRC error indicator in P-CAD PCB, restore the P-CAD PCB window. In the P-CAD PCB window, choose **File** from the menu line and select **Reports**. Then enable **DRC Error Indicators** in the Reports to Generate list and click the **Generate** button.



This produces a report giving the ideal X, Y coordinate location of the termination network on the board together with the values of the component.



A DRC marker is placed in P-CAD PCB adjacent to the pin where the termination network should be applied. If you click on the DRC marker and view its properties (right mouse click and choose **Properties**), you get the value and configuration of the termination network.


# **Run Crosstalk simulation**

The Termination examples given here are for the purpose of demonstrating the tool only and may not be appropriate in the electrical sense.

P-CAD Xtalk, the Crosstalk simulator simulates the coupling between traces with adjacent parallel segments.

P-CAD Signal Integrity is automatically searching for parallel traces, which may cause crosstalk problems. To enter the geometrical parameters for this search, select the **Configure** command from the **Options** menu. Enter the following values:

- Max. Couple Distance: 1mm
- Min. Couple Length: 1mm



Max. Couple Distance specifies the maximum distance, which is used for searching parallel traces. The larger this distance is specified the more parallel traces will be found. Therefore the simulation time will increase.

Min. Couple Length specifies the minimum parallel length of a trace, which is still considered to provide crosstalk. Short parallel segments do not provide much crosstalk, but the simulation time will increase drastically.






Click on the **Get Nets** icon in P-CAD Signal Integrity and then select net DEMO\_D1 in the All Nets column. After that, click on the **Find Coupled Nets** button. Now, all nets within the range of the specification entered in the Options Configure menu will be selected automatically in the All Net list. In this case, these are DEMO\_D0, DEMO\_D1 and DEMO\_D2.




Click the Takeover icon.



- 4
- Next, choose net <code>DEMO\_D1</code> in the simulation window, and click the **Set Victim Net** button. This will set the stimulus for the net <code>DEMO\_D1</code> to constant low level and all other nets will have the default stimulus (single pulse, rising edge at 10ns, falling edge at 60ns). By this, the maximum crosstalk of all coupled nets onto the victim net is calculated.
- 1-1

Now run the Crosstalk simulation by clicking on the **Crosstalk** button.




The WaveAnalyzer shows maximum crosstalk of 1.07V measured on net DEMO\_D1 at pin 3 at component U2. This crosstalk results from the ringing on net DEMO\_D0 and DEMO\_D2 during the signal transition from low to high and high to low.

Close the WaveAnalyzer to return to P-CAD Signal Integrity.




Select net DEMO\_D1 in the Simulation window on the right. Now press the **Set Aggressor Net** icon. By doing this, net DEMO\_D1 will get the default stimulus (single pulse, rising edge at 10ns, falling edge at 60ns) while all other nets will be set to constant low. This will calculate the crosstalk from the aggressor net to all its neighbor nets. After clicking on the **Crosstalk Simulation** button, the WaveAnalyzer displays the results.



# Create a Macromodel

The Macromodel Editor enables you to create your own custom device models. The models are organized in the library tree.

To open the Macromodel Editor, select the **Macromodel Editor** command from the **Library** menu in P-CAD Signal Integrity screen. The library tree displays as shown.




You can navigate through the User Model Library as you do in Windows Explorer.

The library contains a folder for each type of parts and models defined in the database. IC models folders are also sub-divided into folders for each available technology. The full list of technologies available is described in the Macromodel Editor commands' description in chapter 8.


The items in the tree represent user defined custom models.

Let's add a new Resistor component. To do so, click on the Resistor model folder. This displays the currently defined Resistor components (there may be none currently defined).




Choose **Edit** from the Macromodel Editor menu bar and select **Add** from the pull-down menu. This displays the *Modelname Entry* dialog.


Enter Res500 as shown below and click OK.




The *RLC Enter Value* dialog is displayed where you can enter the number of pins. In our case, leave the default value as 2 and click **OK**.



The newly created Resistor Res500 is now displayed on the Library tree.



The Resistor - Res500 dialog is displayed with the information supplied so far and default values for the other parameters.



In this dialog you can change the value in the Using Value box and click the **Apply** button. The entry on the top window will be modified accordingly.


Some IC models in the Library cannot be edited. These models have been created by the P-CAD Signal Integrity IBIS converter and contain data that cannot be modified.

### Create a new Macromodel from an IBIS file

IBIS stands for 'Input/Output Buffer Information Specifications'. It is an ANSI/EIA standard for behavioral specifications of integrated circuit's input/output analog characteristics.

You can create new custom user models based on input from IBIS files.


The Import IBIS File command enables you to do so. The **Import IBIS File** command is accessed from the **Library** pull-down menu on the Signal Integrity entry screen.




Choose the **Import IBIS File** command from the pull-down menu of the **Library** command. This displays the P-CAD IBIS Converter window.

Choose the File command from the menu bar, and select Open on its pull-down menu.

This displays the File Open dialog, choose the  $\P-CAD$  2002  $Demo\Signal$  Integrity folder which includes an example IBIS file.



Choose the file 1vx240db. ibs as shown above. The information is loaded on the IBIS Converter window.



We can now choose which model to generate.

The **Strong Case Model** allows you to test your design performance envelope. The strong case model represents the fast extreme of IC performance.


The **Typical Case Model** lets you get an idea of the typical performance of the design.

Let's choose these two models. To do so, select these two models from the File pull-down menu.

Let's produce a report of these models. Select the **Report** command from the **File** pull-down menu. This displays the *Generate Model Report* dialog, which, by default, allocates for the report the name of the currently opened file. You can modify this or accept this name.



Let's accept the name. This will generate a Word report in the specified directory.




The picture above shows part of the report generated.

Now, let's add these models to the Library.



This is done with the **IBIS File Export** command. It can be accessed from the **File** pull-down menu or by its icon.

When you choose this command, the models are added to the Library. If the models already exist, in the library, a confirmation window is displayed which gives you the option to over-write the currently stored models or cancel your export operation.



Otherwise, an export confirmation message is displayed.

# P-CAD Signal Integrity Command Reference

This Reference chapter provides information on each command, dialog and option available during the simulation process, in the order in which they appear in the menus and dialogs. It also includes additional information about simulation concepts and procedures.

When you start the P-CAD Signal Integrity, the entry screen is displayed, giving you access to process specific icons, menus and commands.



# **File Commands**

The File commands are accessed from the File menu, which appears on the menu bar when you enter P-CAD Signal Integrity. The File commands allow you to open and save files, get nets to analyze and produce reports. Each of these commands is discussed below.

# File Open

The File Open command imports an existing SULTAN file, as input to the simulator, using the Windows standard *File Open* dialog.

A SULTAN file is a representation of the PCB geometry and the required electrical and design specific information (like value of resistors and component designators). This representation is used to store PCB databases so that P-CAD Signal Integrity can be used without having P-CAD PCB open.



The **File Open** command can be initiated from the **File** command pull-down menu or by its icon.

When you choose File Open, P-CAD Signal Integrity displays a dialog from which you can choose the directory and file name of the file you want to open.

The **Look In** area displays the current folder; a list of files in the folder appears directly underneath. The **File name** area lets you select or enter a SULTAN file, from the list of files displayed with the

extension .slt. If a file you want is not in the current directory, you can select another directory from the Directories list.

Once you have made your selection, click the **Open** button.


### File Get Nets

This command displays a list of all nets of the current P-CAD PCB design in the All Nets column of the entry screen. Click on the nets you want to select. These will become highlighted. To select nets, which are not displayed consecutively, press the **Ctrl** button while selecting.

In order to analyze a PCB, P-CAD PCB must be active and a PCB file must be open.



The File Get Nets command can be initiated by choosing **Get Nets** from the **File** pull-down menu or by clicking on its icon.



# File Reports

The File Reports command allows you to output reports with specific output options. These options are saved when you exit the program.



The File Reports command can be initiated by choosing **Reports...** from the **File** pull-down menu or by clicking on its icon. This displays the *File Report* dialog.



#### **Filename**

You can specify individual reports (selecting from the list of report options) and choose to output these all at once or one at a time. Each report type has its own file extension. The file name defaults to the currently open design.

### **Reports File extensions**


These cannot be changed. The extensions used are as follows:

- LAY for Layer Stack information
- NET for Net Data
- XTK for Crosstalk data.


Each of these reports is displayed under Report Options, in the screen report format, which displays a Notepad window.

### **Reports Options**


**Layer Stack** reports the parameters for each layer as listed below.



Net Data reports the parameters and component details for each selected net as listed below.



Crosstalk Data reports the parameters for each selected net as listed below.



### Page Format

These options, when enabled, are output with whatever report type you have chosen to use.

Use Header and Use Footer include the text you have specified in the header and footer fields.

Date/Page includes the current date and page number.

**Pagination** allows you to create your own pagination (lines per page) when you generate the report to the printer or to a file (see Report Destination section below). When you generate the report to the screen, the report is displayed on the Notepad. In this case, use the print command available in the Notepad File command to print the report.

### Style Format

This enables you to specify the format of the report contents.

**Comma Separated** puts all information in comma separated format, which is a spreadsheet-loadable format.

**Report** is a readable format with columns and spaces, etc.

### **Report Destination**

This enables you to specify where to send the output.

**Screen** sends the output to a file and invokes Notepad to display the file. To print this file, use the Notepad File/Print command.

**File** sends the output to a file. The name of the file defaults to the name of the currently open design. You can specify a name of your choice by clicking the *Filename* button. This will display the *Reports File Save* dialog on which you can enter a file name. The file extension will be automatically assigned depending on the type of the report to be generated.




**Printer** sends the output directly to the printer without creating files.

### Lines per Page

This enables you to specify the number of lines per page in your output.

### File SULTAN Out

This command enables you to save the entire current P-CAD PCB design in a SULTAN file. Similar to the File Get Nets command, P-CAD PCB must be active and a PCB database must be open. This command enables the user to load the database later on without any interaction with P-CAD PCB (see command **File Open**).



When you choose **SULTAN Out** from the **File** pull-down menu, the *SULTAN File Name* dialog is displayed and you can specify the directory and filename for the file you want to save.

Enter the file name for the nets. The .slt file type identifying SULTAN files is automatically assigned.

### File Exit

This command exits the P-CAD Signal Integrity Simulator. Before exiting, P-CAD Signal Integrity saves the settings of supply nets, designators and the layer stack as well as the latest simulation options. These will be re-used the next time P-CAD Signal Integrity is started.


# **Edit Commands**

The Edit commands are accessed from the Edit menu, which appears on the menu bar when you enter P-CAD Signal Integrity. They deal with obtaining and modifying the Nets data for the simulation process.

Each of these commands is discussed below.

### **Edit Take Over**

The **Take Over** command acquires the geometric and part data for the nets selected in the left All Nets column from the current P-CAD PCB database. After successful data transfer, these will be displayed in the Simulation windows.





The Edit Take Over command can be initiated from the Edit pull-down menu or by its icon.

The upper window lists the length and average characteristic impedance for each selected net.

The Net Length is the sum of the length of the traces in the net.

The Net Characteristic Impedance is the mean value of the impedance. It is derived from the sum of the impedance of each trace segment multiplied by the length of the trace and divided by the sum of the length of the trace segments.

The lower window displays the components connected to the net selected in the upper window and their characteristics.

### Edit Get PCB Selected Nets



The **Get PCB Selected Nets** command selects those nets in the All Nets column that are currently selected on the PCB in P-CAD PCB.

To use this command first select the net(s) in P-CAD PCB, then chose **Edit** » **Get PCB Selected Nets**, or click the Get PCB Selected Nets icon.

# **Edit Find Coupled Nets**



The **Find Coupled Nets** command analyses the PCB to identify coupled nets, and then selects any coupled nets in the All Nets column.

Coupled nets are identified according to the settings in the *Options Configure* dialog, which defines how close the nets are (couple distance), and the distance that the nets run in parallel (couple length) for them to be considered coupled. Select **Options » Configure** from the menus to set up the coupling properties.

To use this command select a net in the All Nets column, then chose **Edit** » **Find Coupled Nets**, or click the Find Coupled Nets icon. Any coupled nets will be selected in the All Nets column.

# **Edit Layer Stack**

This command enables you to enter or modify the Layer Stack specifications.

The Layer Stack of the PCB must be specified for the calculation of the electrical behavior (characteristic impedance and phase velocity) of the traces.


The required parameters and their default value are listed below:

Parameter details	Default Value
The correct sequence of the layers	None
The thickness of the different copper layers	35 μm
The thickness of the dielectric planes	0.32mm
The dielectric constant of the substrate	$\varepsilon_{\tau} = 4.8$

The Layer Stack and all the calculated transmission line parameters are automatically saved as a .tdb file. This database is stored together with the current PCB project name. It is automatically reused if the same PCB is analyzed in multiple P-CAD Signal Integrity sessions.

Rather than always re-calculating the transmission line characteristics before a new transmission line parameter is calculated, P-CAD Signal Integrity will search its database for an existing set, which matches its current parameters. Whenever the Layer Stack is changed, the old database file gets deleted and a new one is generated.

Choose **Layer Stack** from the **Edit** pull-down menu and the *Layer Stack* dialog is displayed listing all existing layers in your selected design in their current sequence.



This window shows the layer name, the layer type (Signal or Plane) and the layer number as defined by the user in P-CAD PCB.

Here you can modify the Dielectric and Copper property definitions for a layer. To do so, select a layer and enter the changes required in the available entry windows.


When you enter the Copper thickness and the Dielectric value, the Dielectric referred to is the one immediately above the Copper layer. As a result, it is not possible to enter a Dielectric value for the top layer.

All the layers, except the Top and Bottom layers, can be moved up or down by selecting a layer and clicking the appropriate button. The Top layer is always number 1 and the Bottom layer is always number 2 and at the bottom.

Enter changes and click on **OK** for these to take effect.

# **Edit Components**

This command enables you to specify the electrical type of components.



The Components list box contains the names of all components in the active design. You can select individual or multiple components in the list box. Once selected you can specify the electrical type of the components in the Category drop down list.

With the button **To Database** you can save the specified component types to your P-CAD PCB database. The information is saved in the database by a component attribute.

A second way to specify the component type is to define a component attribute directly in P-CAD PCB. Define the Component attribute Category and set the value of the attribute to one of the following qualifier. If you now load the design into P-CAD Signal Integrity, the components get the defined electrical types.


The following electrical component types are supported:

Component Type	Attribute Value
Bipolar Junction Transistor	ВЈТ
Capacitor	Capacitor, Cap
Connector	Connector, Con
Diode	Diode, Dio
IC	IC
Inductor	Inductor, Ind
Resistor	Resistor, Res

The default component type is **IC**.

### **Edit Nets**

This command allows you to specify the name of Supply Nets and their voltage.



Although the Supply Nets cannot be simulated they are necessary for the correct simulation of nets with Pull-up or Pull-down components.


The list box contains the names of all nets in the active design. You can select individual or multiple nets in the list box. Once selected you can specify the category and the voltage of the net.

With the button **To Database** you can save the specified net category and value to your P-CAD PCB database. The information is saved in the database by net attributes.


A second way to specify the net category and value is to define net attributes directly in P-CAD PCB. Define the net attribute **Category** and set the value of the attribute to SUPPLY and the net attribute Voltage and set the value to the voltage of the net. If you now load the design into P-CAD Signal Integrity, the nets get the defined category and value.

### **Edit components specifications**

You can only modify components that are attached to a specific net. Therefore you must select nets from the All Nets column (see display below) and click the **Takeover** icon. P-CAD Signal Integrity then extracts all the required data for these nets and displays these in the simulation windows. You can now select a net in the upper window and select the respective component in the lower window. You can now proceed with the editing as described below.



To modify specifications of components, click on the **Edit Buffer** button under the simulation windows. This displays the relevant component dialog.



You can change the component Model data and the Stimulus pattern.

The Model tab shows the selected component parameters and its current settings. The Part Technology, Input Model and Output Model boxes are context sensitive. When you choose a part technology the default models of the part are taken from this technology. Similarly, choosing a Technology and a direction will automatically display a list of relevant input and/or output models to select from.

Integrated Circuit

Model Stimulus

Stimulus Type: Single Pulse

Load...

Save...

Time

Start Level: Low Total Time: 100 nsec

Stop Time: 60 nsec

Time Step: 100 psec

Cancel

0K

Select a model and click **OK** to apply the changes. To save these changes to the library, click the **Save to Library** button.


On the Stimulus tab you can modify the Stimulus pattern to one of the following: Constant Level, Single pulse or Periodic pulses, and the Stimulus level to: High or Low. The wave display will change to reflect your choices. The number of parameters displayed is context sensitive with the stimulus type chosen. You can also specify Start and Stop times for the pulse and the Period time if a periodic pulse is chosen.

Stimulus details may also be loaded from a file. To do so, click on the **Load** button. This will display the *Load Stimulus* dialog, with the files contained in the current folder. If the file you want is not displayed, you can browse through other directories.



Select the file you want to use and click the **Open** button. This will update the Stimulus with the file data.

Stimulus details can be saved to a file. This is done by clicking the **Save** button, which displays the *Stimulus Save* dialog.



Enter a name for the Stimulus file. The file type .stm is automatically assigned.

# P-CAD Signal Integrity Screening Commands

P-CAD Signal Integrity's screening capability allows you to quickly screen a number of nets for signal integrity and timing effects. It utilizes a very fast 2D-reflection simulator that uses a linear representation of the IC pin behavior to achieve the high speed. It provides you with an overview of the characteristics of the nets that are screened. Besides geometrical information it provides also estimated values for signal integrity effects (overshoot, undershoot).


P-CAD Signal Integrity Screening should be used to determine which nets may be critical and therefore require inspection in greater details using the Reflection simulator.

When screening bi-directional nets, both directions are simulated and the worst result of each effect is displayed.



P-CAD Signal Integrity Screening commands can be accessed by choosing **Screening** from the **Simulation** pull-down menu or by clicking on its icon.

When you start the Screening command, the Screening window is displayed, giving you access to process specific icons, menus and commands.




# **File Commands**

The File commands are accessed from the Screening File menu, which appears on the menu bar when you initiate the Screening command. The File commands allow you to print and save files in different formats. Each of these commands is discussed below.

# File Report

The File Reports command allows you to output reports with specific output options. These options are saved when you exit the program.



#### **Filename**

When choosing a file as the destination for the report, you can specify a file name. The file name defaults to the currently open design. The file extension is automatically assigned depending on the report option chosen.

### Report File extensions

These cannot be changed. The extensions used are as follows:


- NDT for Net Data
- IMP for Impedance Data
- VOL for Voltage Data
- TIM for Timing Data

### **Report Options**


You can specify individual reports (selecting from the list of report options) and choose to output these all at once or one at a time. Each report type has its own file extension. The file name defaults to the currently open design.

The following report examples have been produced choosing the screen as report destination.


Net Data reports the data for each selected net as listed below.




**Impedance Data** reports the impedance readings for each selected net as listed below.



**Voltage Data** reports the voltage readings for the Rising and Falling edges of each selected net as listed below.



**Timing Data** reports the Slope and Flight Time on the Rising and Falling edges for each selected net as listed below.



### **Page Format**

These options, when enabled, are output with whatever report type you have chosen to use.

**Use Header** and **Use Footer** include the text you have specified in the header and footer fields.

**Date/Page** includes the current date and page number.

**Pagination** allows you to create your own pagination (lines per page) when you generate the report to the printer or to a file (see Report Destination section below). When you generate the report to the screen, the report is displayed on the Notepad. In this case, use the DOS print command available in the Notepad File command to print the report.

### **Style Format**

This enables you to specify the format of the report contents.

**Comma Separated** puts all information in comma separated format, which is a spreadsheet-loadable format.

**Report** is a human-readable format with columns and spaces, etc.

### **Report Destination**

This enables you to specify where to send the output.

**Screen** sends the output to a file and invokes Notepad to display the file. To print this file, use the Notepad File/Print command.

**File** sends the output to a file. The name of the file defaults to the name of the currently open design. You can specify a name of your choice by clicking the Filename button. This will display the *Reports File Save* dialog on which you can enter a file name. The file extension will be automatically assigned depending on the report option chosen.

**Printer** sends the output directly to the printer without creating files.

### Lines per Page

This enables you to specify the number of lines per page in your output.


### File SDF Out

This command enables you to save the details on interconnect delays between the different pins of a signal into a SDF file.

The SDF (an abbreviation for Standard Delay Format) file is an ASCII text file that stores the timing data generated by EDA tools. With the SDF intrinsic delays, interconnect delays, loading delays, timing checks and timing constraints are represented using an abstract, tool-independent delay model which is applicable to a variety of tools. The major purpose of the delay file is to facilitate the distribution and control of design delay information between different EDA tools.



The File SDF Out command can be initiated by choosing **SDF Out** ... from the **File** pull-down menu or by clicking on its icon. The *Save File* dialog is displayed, and you can specify the directory and filename for the file you want to save.



Enter a name for your SDF file in the File name box. The SDF file type is automatically assigned.

### File Close

This command exits the Net Screening process.

On exit from the Screening program, Signal Integrity saves the last settings used during the screening session.

# **Edit Commands**

The Screening Edit commands are accessed from the Edit menu, which appears on the menu bar when you initiate the Screening command. They deal with modifying the Screening display.

Each of these commands is discussed below.

### **Edit Delete**

The Edit Delete command removes the selected nets from the display.



The Edit Delete command can be initiated by choosing **Delete** from the **Edit** pull-down menu or by clicking on its icon.

### Edit Select All

The Select All command selects all the nets displayed. The Edit Select All command is initiated by choosing **Select All** from the **Edit** pull-down menu.

### **Edit Invert Selection**

The Invert Selection command redefines the nets selected by substituting the currently selected nets with the currently not-selected nets.

The Edit Invert Selection command is initiated by choosing **Invert Selection** from the **Edit** pull-down menu.

# View Commands


The Screening View commands are accessed from the View menu, which appears on the menu bar when you initiate the Screening command. They deal with selecting and organizing what is displayed on the Screening window and displaying the nets' characteristics.

Each of these commands is discussed below.

### **Net Data View**

The Net Data View displays for each net:

- The net length. This is the sum of the length of the traces
- The number of IC's connected to the traces
- The number of segments for each trace.





The Net Data View command can be initiated by choosing **Net Data View** from the **View** pull-down menu or by clicking on its icon.


You can expand or restrict the columns size by dragging-in or out, at the column separation vertical line on the column header.

# Impedance View

The Impedance View displays for each net:

- The average impedance of the trace. It is derived from. The sum of the impedance of the traces multiplied by the length of the traces and divided by the sum of the length of the traces.
- The minimum impedance of the trace.

• The maximum impedance of the trace.






The View Impedance View command can be initiated by choosing **Impedance View** from the **View** pull-down menu or by clicking on its icon.

# **Voltage View**

The Voltage View displays for each net:

- The Top value of the Rising edge
- The Maximum Overshoot of the Rising edge
- The Maximum Undershoot of the Rising edge
- The Base value of the Falling edge
- The Maximum Overshoot of the Rising edge
- The Maximum Undershoot of the Rising edge






The Voltage View command can be initiated by choosing **Voltage View** from the **View** pull-down menu or by clicking on its icon.

These voltages help you identify the critical nets that will require further investigation with the Reflection Simulator.

# **Timing View**

The Timing View displays for each net:

- The Slope of the Rising edge
- The Flight Time of the Rising edge
- The Slope of the Falling edge
- The Flight Time of the Falling edge





The Timing View command can be initiated by choosing **Timing View** from the **View** pull-down menu or by clicking on its icon.

### **Arrange Nets**

The Arrange Nets command enables you to sort the nets displayed by the value in any of the view columns. The Arrange Nets command is initiated by choosing **Arrange Nets** from the **View** pull-down menu. This displays the Arrange Nets selection menu. The menu displays in highlight the choices currently available. This corresponds to the view displayed.


Select the sorting parameter and the nets displayed will be sorted by the values of that parameter, and displayed in the new sequence.


### Select Columns


The Select Columns command enables you to define what columns should be displayed in each of the Screening views. The Select Columns command is initiated by choosing **Select Columns** from the **View** pull-down menu. This displays the *Select Columns* dialog, which has a tab for each of the Screening views.


The columns currently displayed are ticked. Click on the column(s) to select or de-select.

The dialog below enables you to specify what columns to display on each data view.









# **Help Commands**

The Screening Help commands are accessed from the **Help** menu. They allow you to access all the Help messages.

# **Help Topics**

Displays the P-CAD Signal Integrity online help including the **Contents** tab which is structured to match the order of commands as they appear in the product, and the **Index** tab which lets you look up a specific concept or keyword.

# **About Help**

Connects you to the Windows help system, where instructions on how to use the help system are provided.

# **P-CAD Signal Integrity Simulation Commands**

The Simulator is designed to analyze the behavior of complex transmission line systems on printed circuit boards. You can analyze reflections and crosstalk by simulating nets process takes into account the characteristic impedance and phase velocity of the different segments of a net, which is calculated from the cross-section of the PCB, as well as the input and output characteristics of the buffers connected to this net. For Crosstalk analysis the mutual capacitance and inductance between parallel segments of different nets are considered additionally.

The Simulation commands are accessed from the Simulation menu, which appears on the menu bar when you enter P-CAD Signal Integrity. They deal with reviewing parameters, running simulations and producing outputs.

The Screening command is described in Chapter 5: P-CAD Signal Integrity Screening Commands.

All other Simulation commands are discussed in this chapter.

# **Termination Advisor**

Sometimes termination networks are a good way to prevent reflections, which become prevalent at higher frequencies. These reflections cause noise, which degrade signal integrity and lead to malfunction in the worst case.

Terminations are used to minimize reflection and achieve the signal integrity necessary for successful data integrity.

The Termination Advisor allows you to test termination strategies without making physical changes to your board, by inserting 'virtual terminations' into the net at the location you define.


You can select from a variety of termination options to achieve an optimal PCB electrical performance.



The **Termination Advisor** command can be accessed from the **Simulation** menu or by clicking on its icon


Select a Termination method out of the eight choices available. These are described below:

#### 1. None



No termination is applied. This is the default.

#### 2. Serial R




This is the serial impedance termination method.

A series resistor located at the driver output is a very effective termination technique for point-topoint connections. The value of the amplitude of the incident voltage wave is decreased. The correctly terminated line ( $R1 = Z_L - R_{Out}$ ; ( $Z_L$  characteristic impedance,  $R_{Out}$  output resistance of the buffer) shows no overshoot at the receiver. The series termination is best suited for CMOS technologies.

The value displayed is the default value for the parameter.

#### 3. Parallel R to VCC




With a parallel resistor connected to VCC at the receiver (Pull-up resistor), the input is matched to the transmission line impedance (R1 =  $Z_1$ ). This is a perfect termination for effects due to line reflections, but there is a continuous flow of current through the termination resistor. This increases power dissipation and, depending on the resistor value, leads to increased low voltage levels, which may conflict with 'operation conditions' specified in the component data sheets.

The values displayed are the default values for the parameters.

#### 4. Parallel R to GND


With a parallel resistor connected to GND at the receiver (Pull-down resistor), the receiver input is matched to the transmission line impedance. (R2 = ZL). This is a perfect termination regarding line reflections but there is a continuous current drain through the termination resistor. This increases power dissipation and, depending on the resistor value, leads to decreased high voltage levels, which may conflict with 'operation conditions' specified in the component data sheets.



The value displayed is the default value for the parameter.

#### 5. Parallel R's to VCC and GND


This kind of termination, also called 'Thevenin termination' or 'split termination', can be used for TTL bus systems. With  $R1 \parallel R2 = Z_L$  the termination network is well dimensioned for eliminating transmission line reflections. However the disadvantage of this termination is the large DC current through the resistor divider. In order to avoid violations of datasheet specifications, resistor values should be derived carefully. In most cases a compromise between perfect match and acceptably low current can be achieved.



The values displayed are the default values for the parameters.

#### Parallel C to GND


Sometimes a capacitor to GND is used at the receiver input to reduce signal noise. A disadvantage is that rising and falling waveforms at the receiver may become too smooth and these increases in rise and fall times may cause timing problems.



The value displayed is the default value for the parameter.

#### 7. Parallel R and C to GND


RC termination at the receiver input has the advantage that no DC current flows in the termination network. When the time constant R x C is about four times the propagation delay of the connection, the line is almost sufficiently terminated. For this rule of thumb the value of the resistor is assumed to be equal to the characteristic impedance of the line (R2 =  $Z_1$ ).



The values displayed are the default values for the parameters.

### 8. Parallel Schottky Diodes

Schottky clamping diodes at the end of the transmission line connected to GND and / or VCC reduce under- and overshoot at the receiver. Most input circuits of standard logic ICs contain Schottky clamping diodes.



The value displayed is the default value for the parameter.

## **Set Victim Net**

This command is active only for Crosstalk simulations.



To set a victim net select a net from the list in the Simulation window on the Signal Integrity entry screen and click the Set Victim Net icon, or select **Set Victim Net** from the **Simulation** menu.

A net which is a victim net will have its driving stimulus set to a constant level '0' while all other nets have the stimulus defined in the **Stimulus** tab of the *Integrated Circuit* dialog.

# **Set Aggressor Net**

This command is active only for Crosstalk simulations.



To set an aggressor net select a net from the list in the Simulation window on the Signal Integrity entry screen and click the **Set Aggressor Net** icon or select **Set Aggressor Net** from the **Simulation** menu.

A net which is an aggressor net will have its stimulus defined in the **Stimulus** tab of the *Integrated Circuit* dialog while all other nets are assigned a constant level '0' stimulus.

# Reflection

With high-speed logic design it is becoming increasingly important to ensure that the topology of the PCB interconnect is designed to minimize reflection and crosstalk effects.

Reflection effects are caused by impedance mismatching between components and traces as well as individual trace segments. When traces go from layer to layer impedance discontinuities can occur. Changes in topology such as T-junctions can also cause reflection.

The Reflection simulator calculates voltages at nodes of a net using routing and layer information of the PCB and associated driver and receiver circuits.

The electrical characterization of the lines is automatically calculated by a 2D-field solver. Modeling initially assumes that path losses are small enough to be disregarded.

The simulator provides you with detailed and highly accurate information on all signal integrity related aspects like over- / undershoot, voltage and timing.



The Reflection simulator can be accessed either from the **Simulation** menu by choosing **Reflection** from the pull-down menu or by clicking the mouse button on its icon. This initiates the Reflection simulation for the selected nets.

The results of the Reflection simulation are returned presented in an oscilloscope-like wave analyzer. The WaveAnalyzer commands are described in Chapter 7.

### Crosstalk

The P-CAD Xtalk simulator enables you to analyze crosstalk by simulating coupled nets extracted from PC board circuit layouts.

Crosstalk is a type of interference caused by the electromagnetic waves transmitted from one trace into adjacent traces.




P-CAD Xtalk simulator can be accessed either from the **Simulation** menu by selecting **Crosstalk** from the pull-down menu, or by clicking the mouse button on its icon. This initiates the Crosstalk simulation for the selected nets.

The output of the Crosstalk simulation is displayed by the Wave Analyzer on completion of the simulation.

The time taken to simulate is related to the complexity of the problem being solved. The simulation preparation involves the creation of a  $n^2$  matrix of capacitance and inductance per unit length where n is the number of traces being analyzed.

# P-CAD Signal Integrity Wave Analyzer

P-CAD Signal Integrity Wave Analyzer displays the results of the P-CAD Signal Integrity Reflection or P-CAD Signal Integrity Xtalk simulations in an oscilloscope-like format.



The picture above shows the results of a Reflection simulation. On the right of the wave display wave names are listed under the name of their respective net.

The Wave Analyzer calculates performance parameters like overshoot, rise time, etc. of the nets analyzed. It provides facilities to file, edit and print the results, as well as options to modify the display and zoom-in on areas of interest. The actual values of the parameters can be displayed in the measurement area.

The Wave Analyzer commands are accessed through menus and icons as pictured below. Each command is described in this section.



# **Wave Analyzer File Commands**

The Wave Analyzer File commands deal with opening, saving and printing wave files.


# File Open

The File Open command enables you to load a wave file onto the display.



The **File Open** command can be initiated from the **File** command pull-down menu or by its icon.

When you choose the File Open command, P-CAD Signal Integrity displays the *Open File* dialog from which you can choose the directory and filename of the file you want to open.



Select the wave file you want to use from the files listed. The selection will be shown in the file name box, with the file type .dia. Click the **Open** button and the waves from the file will be added to the current display.

### File Save

Use the File Save command to keep waves details in a file.



The File Save command can be initiated from the File command pull-down menu or by its icon.


When you choose the File Save command, P-CAD Signal Integrity saves the displayed waves and their parameters in the currently open file. If none is opened yet the *Save File* dialog is displayed, on which you can enter a file name. The extension .dia is automatically assigned. This file will be over-written every time you issue a File Save command. If you want to save a wave file with a new file name, use the File Save As command.

### File Save As

The File Save As command saves waves details in a new file with a name and location of your choice.

The **File Save As** command is initiated from the **File** command pull-down menu.

When you choose **File Save As**, the *Save File* dialog is displayed. Here you can specify the directory and filename for the wave file you want to save.



Enter the file name in the File name box, and click the **Save** button. The File type .dia is automatically assigned and the next time you look in the file list the wave file will appear in the file list window with the extension added to the name.


#### File Print

The File Print command prints the current content of the Wave Analyser display.



The File Print command can be initiated from the File command pull-down menu or by its icon.

When you choose the File Print, the *Print* dialog is displayed. Here you can specify the printer and print details.




# File Page Setup


The File Page Setup command enables you to define the page layout details for the printer. It deals with page orientation, margin size and paper size.

The **File Page Setup** command is initiated from the **File** command pull-down menu, and displays the *Page Setup* dialog.

You can specify the paper size and source, and the orientation and margins of the printed page. You can check your layout specification on the page model in the top of the window.



Clicking the **Printer** button displays the following dialog.



### File Exit


The File Exit command closes the Wave Analyzer and returns to the P-CAD Signal Integrity screen.

# **Edit Commands**

The Wave Analyzer Edit commands deal with managing the Wave Analyzer display.

# **Edit Copy**

The **Edit Copy command** is initiated from the **Edit** command pull-down menu. The Edit Copy command copies the displayed waves to the clipboard so that you can load them to another program such as Word. The picture below shows a wave display copied from the Wave Analyzer.



### **Edit Rescale**

The Edit Rescale command rescales the display so that all the full waves fit into the diagram. If you issue the Edit Rescale command when the display is zoomed-in, the display reverts to the original size and scale, *ignoring* any range options specified for the X and Y axes.

The **Edit Rescale** command is initiated from the **Edit** command pull-down menu.

### **Edit Redraw**

The Edit Redraw command redraws the display. The **Edit Redraw** command is initiated from the **Edit** command pull-down menu.

### **Edit Delete Selected Wave**

The Edit Delete Selected Wave command deletes the selected wave. A wave can be selected or deselected by clicking with the mouse on the wave name (on the right of the waves display). The **Edit Delete Selected Wave** command is initiated from the **Edit** command pull-down menu.

### **Edit Delete all Waves**

The Edit Delete all Waves command deletes all the displayed waves. The **Edit Delete all Waves** command can be initiated from the **Edit** command pull-down menu.

### **Edit Clear Measurement Area**


The Edit Clear Measurement Area clears the measurements box which is located on the right of the waves display area. The **Edit Clear Measurement Area** command is initiated from the **Edit** command pull-down menu.

### **Edit Zoom In**

The Edit Zoom In command enables you to zoom-in on sections of the display. Click and hold the mouse button on the top left corner of the area you want to zoom-in on, then move the cursor to the lower right corner of the area and release the mouse button.



The **Edit Zoom In** command can be initiated from the **Edit** command pull-down menu or by its icon. The picture below shows a zoomed-in wave area.



### **Edit Zoom Out**



Use the Edit Zoom Out command to undo the last Zoom In. The **Edit Zoom Out** command can be initiated from the **Edit** command pull-down menu or by its icon.

# **Edit Origin**

Use the Edit Origin command to undo all the Zoom Ins and restore the original waves display. The Edit Origin command maintains the range definitions for the X and Y-axis (set in the Options menu). The **Edit Origin** command is initiated from the **Edit** command pull-down menu.

# **Analyze Commands**

The Wave Analyzer Analyze commands are used to switch between time domain and frequency domain display and to analyze performance parameters of the signal behavior.


# **Analyze Cartes**

The Analyze Cartes command switches the waves display to a Cartesian coordinate system view.

The picture below shows a wave display in Cartesian coordinate system view, which represents the time domain behavior of the signals.



The **Analyze Cartes** command can be initiated from the **Analyze** command pull-down menu or by its icon.




# **Analyze FFT**

The Analyze FFT command switches a wave display to the frequency domain view which is calculated using Fast Fourier Transformation (FFT).

The picture below shows this display method which can be used to analyze the frequency spectrum of the signals. By this, frequencies that may be radiated from the trace with high energy can be detected.



The **Analyze FFT** command can be initiated from the **Analyze** command pull-down menu or by its icon. You must select a wave before you initiate the Analyze FFT command.



Click the Analyze Cartes icon to revert to the Cartesian coordinate system.

### **Analyze Rise Time**

The Analyze Rise Time command displays the rise time of the selected wave in the measurement area. The picture below shows this display.



The **Analyze Rise Time** command can be initiated from the **Analyze** command pull-down menu or by its icon.



This displays the Rise Time for wave U3.5.

# **Analyze Fall Time**

The Analyze Fall Time command displays the fall time of the selected wave in the measurement area. The picture below shows this display.



The **Analyze Fall Time** command can be initiated from the **Analyze** command pull-down menu or by its icon.



This displays the Fall Time for wave U3.5.


# **Analyze Minimum**

The Analyze Minimum command determines the minimum of the selected wave within the currently visible area (zoomed or unzoomed) and displays it in the measurement area.

If there are several minima with the same Y value, the one with the lowest X value is displayed.



The **Analyze Minimum** command can be initiated from the **Analyze** command pull-down menu or by its icon.



This displays the minimum for wave U3.5.


# **Analyze Maximum**

The Analyze Maximum command determines the maximum of the selected wave within the currently visible area (zoomed or unzoomed) and displays it in the measurement area.



The **Analyze Maximum** command can be initiated from the **Analyze** command pull-down menu or by its icon.

If there are several maxima with the same Y value, the one with the lowest X value is displayed.



This displays the maximum for wave U3.5.

# **Analyze Baseline**


The Analyze Baseline command determines the values of the base line for the selected wave and displays these in the measurement area.

These values are the basis for the calculation of the rise and fall times of the slopes of a signal.

In order to calculate the values for the base line a grid is superimposed on the coordinate system and the frequency with which the coordinates occur within the discrete grid cells (events) is evaluated with the aid of a histogram. The lower maximum values of the histogram are the values for the base line. Due to this type of analysis the section in which the slope to be analyzed is displayed is significant. This means the results depend on the zooming.



The **Analyze Baseline** command can be initiated from the **Analyze** command pull-down menu or by its icon.



This displays the base line for wave U3.5.

# **Analyze Topline**

The Analyze Topline command determines the values of the top line for the selected wave and displays these in the measurement area.


These values are the basis for the calculation of the rise and fall times of the slopes of a signal.

In order to calculate the values for the top line a grid is superimposed on the coordinate system and the frequency with which the coordinates occur within the discrete grid cells (events) is

evaluated with the aid of a histogram. The higher maximum values of the histogram are the values for the top line. Due to this type of analysis the section in which the slope to be analyzed is displayed is significant. This means the results depend on the zooming.



The **Analyze Topline** command can be initiated from the **Analyze** command pull-down menu or by its icon.



This displays the top line for wave U3.5.

# **Options Commands**

The Wave Analyzer Options commands deal with modifying the waves display attributes.

### **Options Measurement Area**

The Options Measurement Area command toggles the display of the measurement area. The **Options Measurement Area** command is initiated from the **Options** command pull-down menu.


### **Options Wave Names**

The Options Wave Names command toggles the display of the wave names. The **Options Wave Names** command is initiated from the **Options** command pull-down menu.


# **Options Display**

The Options Display command enables you to set the fonts and colors for the Title, Axis, Wave Names as well as the Background, Foreground and Highlight on the simulation result display area.

The **Options Display** command is initiated from the **Options** command pull-down menu.



Clicking any of the buttons in the Fonts column of the *Options Display* dialog displays the *Font* dialog. This enables you to specify the font characteristics. These take effect when you click the **OK** button.




Clicking any of the buttons in the Colors column of the *Options Display* dialog displays the *Color* dialog. This enables you to specify the background, foreground and highlight colors. They take effect when you click the **OK** button.



# **Options Coordinate System**

The Options Coordinate System command enables you to select the type and line style of the grid and the title of the diagram displayed in the simulation result display area.



The **Options Coordinate System** command is initiated from the **Options** command pull-down menu.


### **Options X-Axis**

The Options X-Axis command enables you to set the range\* of the diagram, the scaling of the X-axis (linear or logarithmic) and the tick density on the axis. The tick density defines also the density of the grid. You can also set the title for the X-axis.

\* Limits for the range: All values (minimum, maximum and step width) must be higher than 1.0e-30 and lower than 1.0e30.

The initial Minimum, Maximum and Step Width values are by default, the values required to fit in all the full waves on the Wave Analyzer display. These are the values that will be restored when issuing the Edit Rescale command.

The **Options X-Axis** command is initiated from the **Options** command pull-down menu.



### **Options Y-Axis**

The Options Y-Axis command enables you to set the range\* of the diagram, the scaling of the Y-axis (linear or logarithmic) and the tick density on the axis. You can also set the title for the Y-axis.


\* Limits for the range: All values (minimum, maximum and step width) must be higher than 1.0e-30 and lower than 1.0e30.

The **Options Y-Axis** command is initiated from the **Options** command pull-down menu.

The maximum must be higher than the minimum. All the values are rounded automatically to the next possible value.

# **Options Wave**

The Options Wave command enables you to set the line style, the line thickness and color and title for the selected wave.



This command operates only when a wave is selected.

The **Options Wave** command is initiated from the **Options** command pull-down menu.

# **Help Commands**

The Wave Analyzer Help commands provide access to the Help messages for all Wave Analyzer commands.

# WaveAnalyser Help Topics

The **Help WaveAnalyzer Help Topics** command is initiated from the **Help** menu.

The Help WaveAnalyzer Help Topics command displays the Wave Analyzer online help including the **Contents** tab which is structured to match the order of commands as they appear in the product, and the index tab which lets you look-up a specific concept or keyword.


# How to Use Help

The **How to Use Help** command is initiated from the **Help** menu.

The How to Use Help command connects you to the Windows help system where instructions on how to use the help system are provided.

# **About WaveAnalyzer**

The **Help About WaveAnalyzer** command is initiated from the **Help** menu. It displays a window with details of the product and the version number.



# **General Commands**

# **Library Commands**

P-CAD Signal Integrity simulation results depend on parts and macromodel specifications. These specifications are looked-up in a database – the model library. This library is split into two sections:

- Basic library
- User library

The Basic library is an integral part of P-CAD Signal Integrity and cannot be modified.

The User library is initially empty and the user can use the Macromodel editor to insert custom models and parts into the model library.


When the simulator looks-up a model or a part (searching is done by name) it first searches the User library. If the desired model or part is not found in the User library, the simulator tries to find in the Basic library. If the model or part is not found in the Basic library either, the simulator uses a fallback model: Fallback model Technology HC.

The Library commands are accessed from the Library menu, which appears on the menu bar on the P-CAD Signal Integrity screen. They deal with editing Macromodels and importing IBIS files.

Each of these commands is discussed below.

# **Macromodel Editor**

Choosing **Macromodel Editor** from the **Library** pull-down menu displays the *Macromodel Editor* window which is similar in appearance and functionality to the Microsoft Windows *Explorer* display.



The editor window is divided into two areas:


- A library tree on the left
- A document area on the right

The custom user models are organized in the library tree. You can navigate through the files system as you do in the Windows Explorer.

# Description of the library tree

The User library is the root of the tree. It contains a folder for each type of parts and models. Each folder holds the list of user custom models defined in the database.

IC models are also sub-divided into available technology folders, as shown in the picture below. Each technology folder holds the custom defined IC buffer models.



The full list of available technologies is in the table below:

Alias	Description
ABT	Advanced Bipolar CMOS Technology
AC	Advanced CMOS
ACT	Advanced CMOS with TTL inputs
AHC	Advanced High Speed CMOS
AHC_50	Advanced High Speed CMOS 5.0V
AHCT	Advanced High Speed CMOS with TTL inputs
AHCT_50	Advanced High Speed CMOS 5.0V with TTL inputs
ALS	Advanced Low Power Schottky
ALVC	Advanced Low Voltage CMOS
AS	Advanced Schottky
ВСТ	Bipolar CMOS Technology
BTL	Backplane Transceiver Logic/Futurebus+
CMOS	CMOS
F	FAST
FCT	FAST CMOS Technology
GTL	Gunning Transceiver Logic
GTL_LVT	Gunning Transceiver Logic Low Voltage
HC	High Speed CMOS
HCT	High Speed CMOS with TTL inputs
HLL	High Speed Low Power Low Voltage CMOS
LS	Low Power Schottky
LV	Low Voltage High Speed CMOS
LVC	Low Voltage CMOS
LVT	Low Voltage BiCMOS Technology
S	Schottky
STD_TTL	Standard TTL
ΠL	ΠL

Unknown technologies (UK) are mapped to HC – (High Speed CMOS).


The items in the tree folders represent user's custom models.

Depending on the type of model you create, view or edit, the appropriate dialog is launched in the area on the right of the library tree.

To view or modify the model parameters you can:

- 1. Double-click on the model name.
- Choose the model name, click the **right** mouse button and select **Open** from the pop-up menu.
- 3. Click once on a model name and choose the **Open** command from the **Edit** pull-down menu.

On the dialog that displays you can view or modify the model parameters.




### IC Models

To create a new model, select a model type or choose a technology for the model, e.g. 'ALS' or 'CMOS' in the appropriate IC folder in the model library, and then select **Add** from the **Edit** menu. After supplying a model name, an IC custom model dialog displays in the area on the right of the Macromodel Editor window. The dialogs vary depending on the model type. There are three tabs to describe the parameters of IC models. Each tab shows the default values for the parameters. You can modify these as required to create your new model.


# IC Input, IC Tristate

IC Input and Tristate dialogs are the same. You can modify parameters by entering them on the relevant tab as described below.


1. The Technology tab. On it you can specify the Supply Voltage for the model.



2. The Resistance and Capacitance tab. On it you specify the Resistance and Capacitance values.



3. The Clamping tab. On this tab you specify the clamping voltage and the differential resistance of the power.



You can save your new model by selecting **Save** on the **Edit** pull-down menu.

Some IC models in the library cannot be edited and some commands are disabled when any of these models are selected. The models have been created and inserted into the library by the P-CAD Signal Integrity IBIS Converter and they contain data that cannot be modified. They are shown in the library to make it complete and to draw your attention to their presence because you cannot create a model with a name already used by an IBIS model. When you double-click an IBIS model, the warning message below is displayed.





You can remove a model by selecting it and doing one of the following:

- Choosing **Delete** for the **Edit** pull-down menu.
- Clicking the **right** button of your mouse and choosing **Delete** from the pop-up menu.

## **IC Output Models**

IC output dialogs have some additional parameters. The Technology and Clamping tabs are the same as for IC Input.







The Resistance and Capacitance tab is different and the Voltage and Timing tab is additional.

On this tab you can specify the output resistance values for low and high states and the capacitance value. Additionally, you can choose between 'push-pull' and 'open-sink' output stages.

For Open Sink output, you must specify the typical Pull-up Resistance and Pull-up Voltage values.




The Voltage and Timing tab is additional. On this tab, you can specify the output voltage values for low and high states and the rise and fall times.



# Resistors, Inductors, Capacitors Models


The view/edit dialog for Resistor, Inductors and Capacitors shows a list of pin connections and their value.




When you create a new Resistor, Inductor or Capacitor you are prompted to specify how many pins the new part will have. For simple resistors, you will use two, and for arrays (several resistors within a part) you will use a number larger than two.

The Resistor Res500 shown below is a simple 2-pin.


Below is an example of a resistor array with 8 pins:



This will show as displayed below:



The picture below shows the default Resistor creation dialog. When you create a new resistor array of 8 pins, the dialog displays no connections.




To assign values to connections, select a pin from the list (this highlights the chosen pin line) and choose a pin to connect to (from the box below the list). Then edit the value of the connection and click the **Apply** button for the assignment to take place.

To delete a connection, select the pin you want to disconnect (the pin line will be highlighted), then choose **None** for the connected pin and click the **Apply** button for the change to take place.

You cannot reduce the number of connections to less than one.

When establishing new connections, you can connect to pins, which already have other pins connected, *only when* the pins already connected to your target pin do not have any other connections established.

For example, you cannot generate the following connections:




Because you would have to do the following connections:

- Connect pin 1 to pin 4 (110 Ohm) → OK
- Connect pin 2 to pin 4 (220 Ohm) → OK
- Connect pin 3 to pin 2 (330 Ohm) → INVALID!


You cannot connect pin 3 to pin 2 because pin 2 is connected to pin 4 and pin 4 has already got connections (connected to pin 1).


The edit dialog for Inductors and Capacitors is similar to the Resistor dialog but the dialog captions are different and other units are used.





### **Diode Models**


The Diode Model dialog has five tabs. When you add a new Diode model, the tabs are filled with default values.












You can modify the parameter fields as required and when you click the **File Close** button, the following dialog is displayed.




Click **Yes** to save the changes you have made.


#### **BJT Transistor**


Here the Edit window has six tabs. When you add a new BJT model, the tabs are filled with default values.


× di


You can modify the parameters as required and when you click the **File Close** button the following dialog is displayed.


















### **Connector (Transmission line)**

When you add a connector TL model, the *Connector* dialog is filled with default values.




You can modify the parameter fields as required and when you click the **File Close** button, the following dialog is displayed.



Click the **Yes** button to save the changes you have made.

### **Connector (Lumped Element)**

This kind of Connector model allows you to modify the number of cascades, Capacitor – Inductor – Capacitor.



You can add or remove cascades by using the Add or Remove buttons.

When you add a new Connector LE, the Connector LE dialog is displayed with default values. You can change the values of the cascade currently selected in the list and assign them by clicking the **Apply** button. When removing cascades at least one cascade must remain.

# **File Commands**

#### File Exit

The Macromodel Editor File Exit command exits the Macromodel Editor program.

### **Edit Commands**

The **Macromodel Editor Edit** commands are accessed from the **Macromodel Editor** menu. They allow you to view, add and make changes to objects in the library.

The Edit menu is context sensitive and is described below in context.

### **Edit Open**

This command is available only when you point to a model component (inside a folder). It opens the model component dialog in the Macromodel Editor right hand side of the display.

#### Edit Add

This command is available only when you point on a folder. It lets you add an item in the current model. When you click the **Add** command, a component model dialog is displayed with default values for the parameters. You can then modify these as required. Further details on adding a component model are listed in each model section above.


Once you are displaying a component model, more Edit commands become available. These commands are described below.

#### **Edit Save**

The Edit Save command lets you save the component model displayed with its current name.

#### **Edit Save As**

The Edit Save As command lets you save the model component displayed as a new component with a different name which you are prompted to enter on the *Input Text* dialog.



#### **Edit Close**

The Edit Close command closes the currently displayed component model.

#### **Edit Delete**

The Edit Delete command deletes the currently displayed (or currently pointed at) component model.

# **Window Commands**

The Macromodel Editor Window commands are accessed from the Macromodel Editor menu. They allow you to manage multiple windows displayed in the right area of the Macromodel Editor. The title of all the open windows are listed on the Window menu box under the menu options.

The window you are working on is the active window and it is shown with a tick on the window titles list. You can move from one window to another by selecting it.

Each of these commands is discussed below.

#### Window Cascade

The Window Cascade command displays all the open windows within the right area of the Macromodel Editor screen so that each window's title is visible.

### Window Arrange Icons

The Window Arrange Icons command arranges minimized windows in the main application window. To minimize a window, click the **Minimize** button in the upper-right corner of the window. You can open one of these minimized icons by double clicking it.

#### Window Next

The Window Next command makes the window next to the currently active window on the right area of the Macromodel Editor screen to become the currently active window and displays it on top of all other windows.

## Import IBIS File

IBIS stands for 'Input/Output' Buffer Information Specifications. It is an ANSI/EIA standard for behavioral specifications of integrated circuit's input/output analog characteristics.

The IBIS Standard is maintained by the IBIS Open Forum which meets monthly via teleconference to discuss updates to the IBIS Standard.

In general IBIS defines the static input and output characteristics as well as values for slew rates for Low/High and High/Low transition. Additionally, the IBIS v3.2 allows the specification of rising and falling waveforms at the output. In IBIS, a reference load is used that consists of lumped elements (resistance, capacitance, inductance and voltage source). Capacitance values for input and output buffers are also specified in IBIS.


The complete IBIS specification and other information about IBIS are available on the IBIS home page:

http://www.eia.org/eig/ibis/ibis.htm

The **Import IBIS File** command is accessed from the **Library** pull-down menu on the Signal Integrity entry screen. When you choose **Import IBIS File**, the P-CAD IBIS Converter window is displayed giving access to its menus and icons.



The icons and menu items are context sensitive; therefore only the commands available at any stage are fully displayed.



Each of these commands is discussed below.

### **IBIS File**

The IBIS File commands are accessed from the menu bar of the IBIS Converter display.

They deal with opening IBIS file creating case models to test IC designs, exporting models and printing reports.


### File Open



The **IBIS File Open** command lets you open an IBIS file. It is accessed from the **File** pull-down menu or by its icon. When you select this command the *Open IBIS File* dialog is displayed.



Click on the file you want to open. The information is then loaded on the IBIS Converter window.



The next three commands deal with models generation. By creating these models you can test the performance of your IC design. These commands are accessed from the **File** pull-down menu or by their icons.

#### **Strong Case Model Generation**



Choosing this model allows you to test your design performance envelope. The Strong Case Model represents the extreme of IC fast performance.

#### **Typical Case Model Generation**



In most cases, Typical model is chosen to get an idea of the typical performance of the design.

#### Weak Case Model Generation




Choosing this model allows you to test your design performance envelope. The Weak Case Model represents the extreme of IC slow performance.

### **Export**




The **IBIS File Export** command allows you to add the current models to the Library. It can be accessed from the **File** pull-down menu or by its icon.

When you choose this command the models are added to the Library. If the models already exist in the Library, a confirmation window is displayed which gives you the option to over-write the currently stored models or cancel your export operation.




The Library entries resulting from the Export are displayed below (st=Strong, tp=Typical, wk=Weak).



### Report

The IBIS File Report command lets you generate a report as a Word document. When you choose this command, the *Generate Model Report* dialog is displayed.



You can enter a name for the report in the File name box. By default, the name of the currently opened IBIS file is displayed.

IBIS Model Info		We	d Jan 31 19:02:45 2001
Component: Buffer: Direction: Model	lvc240 "1" Input LVC240_IN	*******	****
Characteristics C_comp GND Clamp Power Clamp	Best Case typical typical typical	Typ. Case typical typical typical	Worst Case typical typical typical
Component: Buffer: Direction: Model	lvc240 "3" (Input)Tristate LVC240_OUT	*******	****
Characteristics C_comp GND Clamp Power Clamp	Best Case typical typical typical	<b>Typ. Case</b> typical typical typical	Worst Case typical typical typical

The picture above shows part of the report generated.

#### **Exit**

This command closes the IBIS Converter program.

# **Options Commands**


Signal Integrity Options commands deal with specifying net attributes, simulation parameters and configuration details.

The Options commands are accessed from the Options menu in P-CAD Signal Integrity.

Each of these commands is discussed below.

# Configure

When you select this command, the Options Configure dialog appears.



#### Crosstalk

You can set the parameter used for search of parallel traces for the crosstalk simulation. Max. Couple Distance specifies the maximum distance, which is used for searching parallel traces. The larger this distance is specified, the more parallel traces will be found. Therefore the simulation time will increase. Min. Couple Length specifies the minimum parallel length of a trace, which is still considered to provide crosstalk. Short parallel segments do not provide much crosstalk, but the simulation time will increase drastically.

#### **Net Simplify**

You can define the length of stubs (short open traces) to exclude from the simulation. Short stubs will increase the simulation time drastically.

#### Units

You can alter your display units between mils and milllimeter with this option. Dimensions are not altered, only the unit of measurements of dimension. A *mil* equals 0.001 inch or 0.0254 mm. A *mm* equals 0.001 meter.

#### **Highlight Nets in P-CAD PCB**

If you choose the Highlight Nets in P-CAD PCB option, any nets selected in the All Nets column of the Signal Integrity screen are automatically highlighted in P-CAD PCB.

The settings are saved when you exit the Signal Integrity program.


#### Simulator

This command enables you to specify the Simulator options. All the Simulator option settings are saved when you exit the Signal Integrity program.

To choose this command, select **Simulator** from the **Options** pull-down menu. This displays a three tab dialog.

### **Simulator Integration**

Click on the **Integration** tab to choose one of the four different numerical integration algorithms for the simulator.




Trapezoidal Integration is the default integration algorithm.

Choose the algorithm you require and click **OK**.

#### **Simulator Accuracy**

Click on the **Accuracy** tab to enter values for:

Keyword	Default	Description
RELTOL	1.0e-3	Relative Tolerance for calculating current voltage values
ABSTOL	1.02-12	Absolute tolerance for calculating current values
VNTOL	1.0e-6 V	Absolute tolerance for calculating voltage values
TRTOL	10	Factor of estimating error of integration
NRVABS	1.0e-3	Truncation error bound using Newton-Raphson algorithm
DTMIN	1.0e-15	Minimum permitted time step size
ITL	100	Maximum number of iterations using Newton-Raphson algorithm
LIMPTS	1000	Maximum number of value pairs in output file for each voltage curve




#### **Simulator DC Analysis**

Click on the **DC Analysis** tab to enter values for:

Keyword	Default	Description	
RAMP_FACT	80	Control of ramp's length during the DC-analysis	
DELTA_DC	1.0e-9	Time-step width used for DC-analysis	
ZLINE_DC	100 Ohm	Transmission line impedance of the lines during the DC-analysis	
ITL_DC	10000	Maximum number of iterations during the DC-analysis	
DELTAV_DC	1.0e-4 V	Absolute tolerance of voltages between two time-steps during the DC-analysis	
DELTA_DC	1.0e-6 A	Absolute tolerance of currents between two time-steps during the DC-analysis	
DV_ITERAT_DC	0.1 V	Absolute tolerance of voltages per iteration during the DC-analysis	

Enter the values on the relevant window and click **OK** for these to be applied.



# **Help Commands**

Signal Integrity includes online reference help but differs from the manuals in its format and accessibility.

The main advantages of online help are the availability of *hypertext links* between related subjects (an electronic cross-reference utility) and the keyword search function (an electronic index).

### Signal Integrity Help Topics


Displays the P-CAD Signal Integrity online help including **Contents** tab which is structured to match the order of the commands as they appear in the product, and the **Index** tab which lets you look-up a specific concept or keyword.

### How to use Help

Connects you to the Windows help system where instructions on how to use the help system are provided.

### **About P-CAD Signal Integrity**

Displays a dialog that contains information such as the product version number, release date, memory used, memory available and license details.



# **List of Signal Integrity Digital Integrated Circuits**

This appendix lists all the Digital Integrated Circuits included in P-CAD Signal Integrity and explains the process of searching the Signal Integrity Device Library.

# **Signal Integrity Device Library**

The P-CAD Signal Integrity Device Library consists of two major parts:

1. A Base area

It contains electrical oriented device descriptions and simulation models. This data cannot be modified by the user.

2. A User area

Initially this area is empty. It is used to store any user driven extension or modification of Signal Integrity Library contents.

# Signal Integrity Device Handling/Search

When P-CAD Signal Integrity is searching PCB data initially the library module is called to get the necessary electrical parameters and simulation models.

The following classes of devices are considered:

- Digital Integrated Circuits
- Connectors
- Capacitors
- Coils
- Resistors

#### Appendix A: Digital Integrated Circuits included in P-CAD Signal Integrity

Devices, which could not be assigned to one of the named classes, are handled as Digital Integrated Circuits.

The primary Signal Integrity library access key is the device name used inside the design data. If a design device exactly matches a Signal Integrity library device, the latter's electrical parameters and simulation models will be used to perform the analysis.

When there is no direct match in a second search step for each not already found device, the first more or less similar named device of the Signal Integrity library is used as reference. Example:

- design name '74ABT244' matches Signal Integrity library device 'SN74ABT244DB',
- design name 'ALVC16240' matches Signal Integrity library device '74ALVC16240DGG'.

If the second step search fails to find a nearly similar named device, the device type and associated technology fallbacks are used to guarantee the proper functioning of the simulators.

In all cases of searching data, the pin count and the device type are taken into account.

All search operations start on the user area.

# Digital Integrated Circuits included in P-CAD Signal Integrity

There are 4474 Digital Integrated Circuit components in the library. These are listed here in alphabetical order.

4SN74ACT534PW	74ALVC16652DL	74LV04D
4SN74LVC257DW	74ALVC16952DGG	74LV04N
74ALVC16240DGG	74ALVC16952DL	74LV08D
74ALVC16240DL	74HL33240D	74LV08N
74ALVC16241DGG	74HL33240DB	74LV123D
74ALVC16241DL	74HL33241D	74LV123N
74ALVC16244DGG	74HL33241DB	74LV125D
74ALVC16244DL	74HL33244D	74LV125N
74ALVC16245DGG	74HL33244DB	74LV132D
74ALVC16245DL	74HL33245D	74LV132N
74ALVC16373DGG	74HL33245DB	74LV138D
74ALVC16373DL	74HL33373D	74LV138N
74ALVC16374DGG	74HL33373DB	74LV139D
74ALVC16374DL	74HL33374D	74LV139N
74ALVC164245DGG	74HL33374DB	74LV14D
74ALVC164245DL	74HL33533D	74LV14N

Appendix A: Digital Integrated Circuits included in P-CAD Signal Integrity

74ALVC16500DGG	74HL33533DB	74LV157D
74ALVC16500DL	74HL33534D	74LV157N
74ALVC16501DGG	74HL33534DB	74LV161D
74ALVC16501DL	74HL33620D	74LV161N
74ALVC16540DGG	74HL33620DB	74LV163D
74ALVC16540DL	74HL33623D	74LV163N
74ALVC16541DGG	74HL33623DB	74LV164D
74ALVC16541DL	74HL33640D	74LV164N
74ALVC16543DGG	74HL33640DB	74LV174D
74ALVC16543DL	74HL33646D	74LV174N
74ALVC16600DGG	74HL33646DB	74LV240D
74ALVC16600DL	74HL33652D	74LV240DB
74ALVC16601DGG	74HL33652DB	74LV240N
74ALVC16601DL	74HL33952D	74LV244D
74ALVC16623DGG	74HL33952DB	74LV244DB
74ALVC16623DL	74LV00D	74LV244N
74ALVC16646DGG	74LV00N	74LV245D
74ALVC16646DL	74LV02D	74LV245DB
74ALVC16652DGG	74LV02N	74LV245N
74LV259D	74LVC02PW	74LVC2952DB
74LV259N	74LVC04D	74LVC2952PW
74LV273D	74LVC04DB	74LVC32D
74LV273DB	74LVC04PW	74LVC32DB
74LV273N	74LVC08D	74LVC32PW
74LV32D	74LVC08DB	74LVC373D
74LV32N	74LVC08PW	74LVC373DB
74LV365D	74LVC109D	74LVC373PW
74LV365N	74LVC109DB	74LVC374D
74LV368D	74LVC109PW	74LVC374DB
74LV368N	74LVC125D	74LVC374PW
74LV373D	74LVC125DB	74LVC38D
74LV373DB	74LVC125PW	74LVC38DB
74LV373N	74LVC137D	74LVC38PW
·		

Appendix A: Digital Integrated Circuits included in P-CAD Signal Integrity

74LV374D	74LVC137N	74LVC4245D
74LV374DB	74LVC138D	74LVC4245DB
74LV374N	74LVC138DB	74LVC4245PW
74LV377D	74LVC138PW	74LVC543D
74LV377DB	74LVC139D	74LVC543DB
74LV377N	74LVC139DB	74LVC543PW
74LV541D	74LVC139PW	74LVC544D
74LV541DB	74LVC157D	74LVC544DB
74LV541N	74LVC157DB	74LVC544PW
74LV573D	74LVC157PW	74LVC573D
74LV573DB	74LVC240D	74LVC573DB
74LV573N	74LVC240DB	74LVC573PW
74LV574D	74LVC240PW	74LVC574D
74LV574DB	74LVC241D	74LVC574DB
74LV574N	74LVC241DB	74LVC574PW
74LV595D	74LVC241PW	74LVC623D
74LV595N	74LVC244D	74LVC623DB
74LV74D	74LVC244DB	74LVC623PW
74LV74N	74LVC244PW	74LVC646D
74LV86D	74LVC245D	74LVC646DB
74LV86N	74LVC245DB	74LVC646PW
74LVC00D	74LVC245PW	74LVC652D
74LVC00DB	74LVC257D	74LVC652DB
74LVC00PW	74LVC257DB	74LVC652PW
74LVC02D	74LVC257PW	74LVC74D
74LVC02DB	74LVC2952D	74LVC74DB
74LVC74PW	MACH110-12JC	PAL16R4DCJ
74LVC821D	MACH110-15CQFPC	PAL16R4DCN
74LVC821DB	MACH110-15JC	PAL16R4DCNL
74LVC821PW	MACH120-15CQFPC	PAL16R6-5JC
74LVC823D	MACH120-15JC	PAL16R6-5PC
74LVC823DB	MACH130-15CQFPC	PAL16R6A-2CJ
74LVC823PW	MACH130-15JC	PAL16R6A-2CN

Appendix A: Digital Integrated Circuits included in P-CAD Signal Integrity

74LVC827D	MACH210-12CQFPC	PAL16R6A-2CNL
74LVC827DB	MACH210-12JC	PAL16R6B-2CJ
74LVC827PW	MACH210-15CQFPC	PAL16R6B-2CN
74LVC841D	MACH210-15JC	PAL16R6B-2CNL
74LVC841DB	MACH220-15CQFPC	PAL16R6B-4CJ
74LVC841PW	MACH220-15JC	PAL16R6B-4CN
74LVC86D	MACH230-15CQFPC	PAL16R6B-4CNL
74LVC86DB	MACH230-15JC	PAL16R6DCJ
74LVC86PW	PAL16L8-5JC	PAL16R6DCN
74LVU04D	PAL16L8-5PC	PAL16R6DCNL
74LVU04N	PAL16L8A-2CJ	PAL16R8-5JC
AmPAL22V10/ADC	PAL16L8A-2CN	PAL16R8-5PC
AmPAL22V10/AJC	PAL16L8A-2CNL	PAL16R8A-2CJ
AmPAL22V10/APC	PAL16L8B-2CJ	PAL16R8A-2CN
CDC209-7DW	PAL16L8B-2CN	PAL16R8A-2CNL
CDC209-7N	PAL16L8B-2CNL	PAL16R8B-2CJ
CDC209DW	PAL16L8B-4CJ	PAL16R8B-2CN
CDC209N	PAL16L8B-4CN	PAL16R8B-2CNL
CDC337DB	PAL16L8B-4CNL	PAL16R8B-4CJ
CDC337DW	PAL16L8DCJ	PAL16R8B-4CN
CDC340DB	PAL16L8DCN	PAL16R8B-4CNL
CDC340DW	PAL16L8DCNL	PAL16R8DCJ
CDC341DB	PAL16R4-5JC	PAL16R8DCN
CDC341DW	PAL16R4-5PC	PAL16R8DCNL
GAL16V8B-7J	PAL16R4A-2CJ	PAL20L8-5JC
GAL16V8B-7P	PAL16R4A-2CN	PAL20L8-5PC
GAL16V8H-152C	PAL16R4A-2CNL	PAL20L8A-2CJS
GAL16V8H-15JC	PAL16R4B-2CJ	PAL20L8A-2CNL
GAL16V8H-15PC	PAL16R4B-2CN	PAL20L8A-2CNS
GAL16V8H-15RC	PAL16R4B-2CNL	PAL20L8B-2CFN
GAL20V8B-7J	PAL16R4B-4CJ	PAL20L8B-2CJS
GAL20V8B-7P	PAL16R4B-4CN	PAL20L8B-2CNS
MACH110-12CQFPC	PAL16R4B-4CNL	PAL20R4-5JC

Appendix A: Digital Integrated Circuits included in P-CAD Signal Integrity

PAL20R4-5PC	SN7403J	SN7412J
PAL20R4A-2CJS	SN7403N	SN7412N
PAL20R4A-2CNL	SN7404J	SN74130J
PAL20R4A-2CNS	SN7404N	SN74130N
PAL20R4B-2CFN	SN7405J	SN74132J
PAL20R4B-2CJS	SN7405N	SN74132N
PAL20R4B-2CNS	SN7406J	SN74136J
PAL20R6-5JC	SN7406N	SN74136N
PAL20R6-5PC	SN7407J	SN7413J
PAL20R6A-2CJS	SN7407N	SN7413N
PAL20R6A-2CNL	SN7408J	SN74141J
PAL20R6A-2CNS	SN7408N	SN74141N
PAL20R6B-2CFN	SN7409J	SN74143J
PAL20R6B-2CJS	SN7409N	SN74143N
PAL20R6B-2CNS	SN74100J	SN74144J
PAL20R8-5JC	SN74100N	SN74144N
PAL20R8-5PC	SN74107J	SN74145J
PAL20R8A-2CJS	SN74107N	SN74145N
PAL20R8A-2CNL	SN74109J	SN74147J
PAL20R8A-2CNS	SN74109N	SN74147N
PAL20R8B-2CFN	SN7410J	SN74148J
PAL20R8B-2CJS	SN7410N	SN74148N
PAL20R8B-2CNS	SN74111J	SN7414J
PAL22V10-153C	SN74111N	SN7414N
PAL22V10-15JC	SN74116J	SN74150J
PAL22V10-15KC	SN74116N	SN74150N
PAL22V10-15LC	SN74120J	SN74151AJ
PAL22V10-15PC	SN74120N	SN74151AN
PALC22V10-25JC	SN74121J	SN74153J
PALC22V10-25PC	SN74121N	SN74153N
PALC22V10-25WC	SN74122J	SN74154J
PALC22V10B-15JC	SN74122N	SN74154N
PALC22V10B-15PC	SN74123J	SN74155J

Appendix A: Digital Integrated Circuits included in P-CAD Signal Integrity

SN7400J         SN74125J         SN74156J           SN7400N         SN74125N         SN74156N           SN7401J         SN74126J         SN74157J           SN7401N         SN74126N         SN74157J           SN7401N         SN74126N         SN74157N           SN7402N         SN74128J         SN74159J           SN7402N         SN74128N         SN74159N           SN74160J         SN74181J         SN74259N           SN74160N         SN74181J         SN74259N           SN74160N         SN74181N         SN7425N           SN74161J         SN74182J         SN7425N           SN74161N         SN74182J         SN7425N           SN74161N         SN74182J         SN7425N           SN74161N         SN74182J         SN74265J           SN74162J         SN74182J         SN74265J           SN74162J         SN74184M         SN74265           SN74162J         SN74185AJ         SN74260           SN74163J         SN74185AJ         SN74273J           SN74164J         SN74185AN         SN74273J           SN74164J         SN74190J         SN74276N           SN74165J         SN74191N         SN74276N	PALC22V10B-15WC	SN74123N	SN74155N
SN7401J         SN74126J         SN74157J           SN7401N         SN74126N         SN74157N           SN7402J         SN74128J         SN74159J           SN7402N         SN74128N         SN74159J           SN74160J         SN74181J         SN74259N           SN74160J         SN74181J         SN74259N           SN74160N         SN74181N         SN7425J           SN74161J         SN74182J         SN7425J           SN74161J         SN74182J         SN7425N           SN74161J         SN74182N         SN7426J           SN74161N         SN74182N         SN74265J           SN74162J         SN741844I         SN74265J           SN74162J         SN741844I         SN74265J           SN74162N         SN74185AJ         SN7426B           SN74163J         SN74185AJ         SN7426B           SN74163J         SN74185AJ         SN7426B           SN74163N         SN74185AN         SN74273J           SN74164J         SN74190J         SN74273J           SN74164H         SN74190J         SN74276B           SN74165J         SN74191         SN74276B           SN74166N         SN74193J         SN74279B	SN7400J	SN74125J	SN74156J
SN7401N         SN74126N         SN74157N           SN7402J         SN74128J         SN74159J           SN7402N         SN74128N         SN74159N           SN74160J         SN74181J         SN74259N           SN74160N         SN74181N         SN74259N           SN74161D         SN74182J         SN7425N           SN74161J         SN74182J         SN7425N           SN74161N         SN74182N         SN7426J           SN74162D         SN74182N         SN7426J           SN74162J         SN74184H         SN7426SN           SN74162J         SN74184N         SN7426SN           SN74162N         SN74184N         SN7426GN           SN74163J         SN74185AJ         SN7426N           SN74163J         SN74185AN         SN74273J           SN74164J         SN74190J         SN74273J           SN74164H         SN74190J         SN74273N           SN74164H         SN74191J         SN74276           SN74165J         SN74191N         SN74276N           SN74165N         SN74192J         SN74278           SN74166N         SN74193J         SN74278N           SN7416N         SN74193N         SN74279N	SN7400N	SN74125N	SN74156N
SN7402J         SN74128J         SN74159J           SN7402N         SN74128N         SN74159N           SN74160J         SN74181J         SN74259N           SN74160N         SN74181J         SN74259N           SN74160N         SN74181N         SN74259N           SN74161J         SN74182J         SN7425N           SN74161J         SN74182J         SN7425N           SN74161N         SN74182N         SN74265J           SN74162J         SN74184J         SN74265J           SN74162D         SN74184M         SN7426J           SN74162N         SN74185AJ         SN7426J           SN74163J         SN74185AN         SN74273J           SN74163N         SN74185AN         SN74273J           SN74164M         SN74190J         SN74273J           SN74164M         SN74191J         SN74276J           SN74164M         SN74191J         SN74276J           SN74165J         SN74191N         SN74276N           SN74165N         SN74192J         SN74278J           SN74166J         SN74192N         SN74278N           SN74166N         SN74193N         SN74279J           SN7416N         SN74194N         SN74279N	SN7401J	SN74126J	SN74157J
SN7402N         SN74128N         SN74159N           SN74160J         SN74181J         SN74259N           SN74160N         SN74181N         SN7425J           SN74161J         SN74182J         SN7425N           SN74161J         SN74182J         SN7425N           SN74161M         SN74182J         SN7425N           SN74161M         SN74182N         SN74265J           SN74162J         SN74184J         SN74265N           SN74162J         SN74184M         SN74265N           SN74162N         SN74184M         SN7426J           SN74163J         SN74185AJ         SN7426J           SN74163J         SN74185AN         SN74273J           SN74163M         SN74185AN         SN74273J           SN74164H         SN74190J         SN74273N           SN74164H         SN74191J         SN74276I           SN74165J         SN74191N         SN74276I           SN74165N         SN74192J         SN74278I           SN74166N         SN74192N         SN74278N           SN74166N         SN74193J         SN74279I           SN7416N         SN74193N         SN74279N           SN7416N         SN74194N         SN7427N	SN7401N	SN74126N	SN74157N
SN74160J         SN74181J         SN74259N           SN74160N         SN74181N         SN7425J           SN74161J         SN74182J         SN7425N           SN74161N         SN74182N         SN74265J           SN74161N         SN74182N         SN74265J           SN74162J         SN74184J         SN74265N           SN74162J         SN74184N         SN7426J           SN74163J         SN74185AJ         SN7426N           SN74163J         SN74185AJ         SN74273J           SN74163N         SN74185AN         SN74273J           SN74164J         SN74190J         SN74273N           SN74164M         SN74191J         SN74276J           SN74165J         SN74191N         SN74276N           SN74165N         SN74192J         SN74278J           SN74166N         SN74192N         SN74278N           SN74166N         SN74193J         SN74279J           SN74167J         SN74193N         SN74279N           SN7416N         SN74194J         SN7427N           SN7416N         SN74195J         SN74283J           SN7416N         SN74195N         SN74283N           SN74170J         SN74195N         SN74283N	SN7402J	SN74128J	SN74159J
SN74160N         SN74181N         SN7425J           SN74161J         SN74182J         SN7425N           SN74161N         SN74182N         SN74265J           SN74161N         SN74182N         SN74265J           SN74162J         SN74184N         SN74265N           SN74162J         SN74184N         SN7426N           SN74163J         SN74185AJ         SN7426N           SN74163J         SN74185AN         SN74273J           SN74163N         SN74185AN         SN74273J           SN74164J         SN74190J         SN74273N           SN74164H         SN74191J         SN74276J           SN74165J         SN74191N         SN74276J           SN74165J         SN74191N         SN74278J           SN74166J         SN74192J         SN74278N           SN74166J         SN74193J         SN74279J           SN74167J         SN74193N         SN74279N           SN74160J         SN74194J         SN7427J           SN7416N         SN74194J         SN7427N           SN7416N         SN74195J         SN74283J           SN74170J         SN74195N         SN74283J           SN74170J         SN74196N         SN74284N	SN7402N	SN74128N	SN74159N
SN74161J         SN74182J         SN7425N           SN74161N         SN74182N         SN74265J           SN74162J         SN74184J         SN74265N           SN74162N         SN74184N         SN74265N           SN74162N         SN74184N         SN7426J           SN74163J         SN74185AJ         SN7426N           SN74163N         SN74185AN         SN74273J           SN74164J         SN74190J         SN74273N           SN74164J         SN74190J         SN74278J           SN74164N         SN74191J         SN74276J           SN74165J         SN74191N         SN74276I           SN74165J         SN74192J         SN74278J           SN74165N         SN74192N         SN74278J           SN74166J         SN74193J         SN74278N           SN7416O         SN74193N         SN74279N           SN7416O         SN74194J         SN7427J           SN7416J         SN74194N         SN7427N           SN7416N         SN74195J         SN74283J           SN74170J         SN74195N         SN74283N           SN74170N         SN74196N         SN74284N           SN74172D         SN74197J         SN74285D	SN74160J	SN74181J	SN74259N
SN74161N         SN74182N         SN74265J           SN74162J         SN74184J         SN74265N           SN74162N         SN74184N         SN7426J           SN74163J         SN74185AJ         SN7426N           SN74163N         SN74185AN         SN74273J           SN74164N         SN74190J         SN74273N           SN74164J         SN74190J         SN74273N           SN74164N         SN74191J         SN74276J           SN74165J         SN74191N         SN74276J           SN74165J         SN74191N         SN74276N           SN74165N         SN74192J         SN74278J           SN74166N         SN74193J         SN74278J           SN74166N         SN74193N         SN74279J           SN74167I         SN74193N         SN74279J           SN7416N         SN74194J         SN7427N           SN7416D         SN74194N         SN7427N           SN7416N         SN74195J         SN74283J           SN74170J         SN74195N         SN74283N           SN74170N         SN74196J         SN74284J           SN74172D         SN74196N         SN74285J           SN74173J         SN74197N         SN74285N	SN74160N	SN74181N	SN7425J
SN74162J         SN74184J         SN74265N           SN74162N         SN74184N         SN7426J           SN74163J         SN74185AJ         SN7426N           SN74163N         SN74185AN         SN74273J           SN74164J         SN74190J         SN74273N           SN74164J         SN74190J         SN74273N           SN74164N         SN74191J         SN74276J           SN74165J         SN74191N         SN74276I           SN74165J         SN74191N         SN74276N           SN74165N         SN74192J         SN74278J           SN74166I         SN74192N         SN74278I           SN74166N         SN74193J         SN74279J           SN74167J         SN74193N         SN74279I           SN74167N         SN74194J         SN7427I           SN7416N         SN74194J         SN7427N           SN7416N         SN74195J         SN74283J           SN74170J         SN74195N         SN74283N           SN74170N         SN74196J         SN74284J           SN74172I         SN74197J         SN74285J           SN74173J         SN74197N         SN74285N           SN74173N         SN74198J         SN7428N	SN74161J	SN74182J	SN7425N
SN74162N         SN74184N         SN7426J           SN74163J         SN74185AJ         SN7426N           SN74163N         SN74185AN         SN74273J           SN74164J         SN74190J         SN74273N           SN74164N         SN74190J         SN74276J           SN74164N         SN74191J         SN74276J           SN74165J         SN74191N         SN74276N           SN74165N         SN74192J         SN74278J           SN74166J         SN74192N         SN74278N           SN74166N         SN74193J         SN74279J           SN74167J         SN74193N         SN74279N           SN74167N         SN74194J         SN7427J           SN7416N         SN74194N         SN7427N           SN7416N         SN74195J         SN74283J           SN74170J         SN74195N         SN74283N           SN74170N         SN74196J         SN74284J           SN74172J         SN74196N         SN74284N           SN74173J         SN74197N         SN74285           SN74173N         SN74198J         SN7428I           SN74174J         SN74198N         SN7428N	SN74161N	SN74182N	SN74265J
SN74163J         SN74185AJ         SN7426N           SN74163N         SN74185AN         SN74273J           SN74164J         SN74190J         SN74273N           SN74164N         SN74191J         SN74276J           SN74165J         SN74191N         SN74276N           SN74165J         SN74191N         SN74276N           SN74165N         SN74192J         SN74278J           SN74166J         SN74192N         SN74278N           SN74166N         SN74193J         SN74279J           SN74167J         SN74193N         SN74279N           SN74167N         SN74194J         SN7427J           SN7416D         SN74194J         SN7427N           SN7416N         SN74195J         SN74283J           SN74170J         SN74195N         SN74283N           SN74170N         SN74196N         SN74284J           SN74172J         SN74196N         SN74284N           SN74173N         SN74197N         SN74285N           SN74173N         SN74198J         SN7428N	SN74162J	SN74184J	SN74265N
SN74163N         SN74185AN         SN74273J           SN74164J         SN74190J         SN74273N           SN74164N         SN74191J         SN74276J           SN74165J         SN74191N         SN74276N           SN74165N         SN74192J         SN74278J           SN74166N         SN74192N         SN74278N           SN74166N         SN74193J         SN74279J           SN74167J         SN74193N         SN74279N           SN74167N         SN74194J         SN7427J           SN7416J         SN74194N         SN7427N           SN7416N         SN74195J         SN7428J           SN74170J         SN74195N         SN74283N           SN74170N         SN74196J         SN74284J           SN74172J         SN74196N         SN74284N           SN74172N         SN74197J         SN74285J           SN74173J         SN74197N         SN74285N           SN74173J         SN74198J         SN7428I           SN74174J         SN74198N         SN7428N	SN74162N	SN74184N	SN7426J
SN74164J         SN74190J         SN74273N           SN74164N         SN74191J         SN74276J           SN74165J         SN74191N         SN74276N           SN74165N         SN74192J         SN74278J           SN74166N         SN74192N         SN74278N           SN74166N         SN74193J         SN74279J           SN74167J         SN74193N         SN74279N           SN74167N         SN74194J         SN7427J           SN7416J         SN74194N         SN7427N           SN7416N         SN74195J         SN74283J           SN74170J         SN74195N         SN74283N           SN74170N         SN74196J         SN74284J           SN74172J         SN74196N         SN74284N           SN74173J         SN74197N         SN74285J           SN74173N         SN74198J         SN7428J           SN74174J         SN74198N         SN7428N	SN74163J	SN74185AJ	SN7426N
SN74164N         SN74191J         SN74276J           SN74165J         SN74191N         SN74276N           SN74165N         SN74192J         SN74278J           SN74166J         SN74192N         SN74278J           SN74166J         SN74192N         SN74278N           SN74166N         SN74193J         SN74279J           SN74167J         SN74193N         SN74279N           SN74167N         SN74194J         SN7427J           SN7416J         SN74194N         SN7427N           SN7416N         SN74195J         SN74283J           SN74170J         SN74195N         SN74283N           SN74170N         SN74196J         SN74284J           SN74172J         SN74196N         SN74284N           SN74173J         SN74197N         SN74285J           SN74173N         SN74198J         SN7428J           SN74174J         SN74198N         SN7428N	SN74163N	SN74185AN	SN74273J
SN74165J         SN74191N         SN74276N           SN74165N         SN74192J         SN74278J           SN74166J         SN74192N         SN74278N           SN74166N         SN74193J         SN74279J           SN74167J         SN74193N         SN74279N           SN74167N         SN74194J         SN7427J           SN7416J         SN74194N         SN7427N           SN7416N         SN74195J         SN74283J           SN74170J         SN74195N         SN74283N           SN74170N         SN74196J         SN74284J           SN74172J         SN74196N         SN74284N           SN74173J         SN74197N         SN74285N           SN74173N         SN74198J         SN7428I           SN74174J         SN74198N         SN7428N	SN74164J	SN74190J	SN74273N
SN74165N         SN74192J         SN74278J           SN74166J         SN74192N         SN74278N           SN74166N         SN74193J         SN74279J           SN74167J         SN74193N         SN74279N           SN74167N         SN74194J         SN7427J           SN7416J         SN74194N         SN7427N           SN7416N         SN74195J         SN74283J           SN74170J         SN74195N         SN74283N           SN74170N         SN74196J         SN74284J           SN74172J         SN74196N         SN74284N           SN74172N         SN74197J         SN74285J           SN74173J         SN74197N         SN74285N           SN74173N         SN74198J         SN7428I           SN74174J         SN74198N         SN7428N	SN74164N	SN74191J	SN74276J
SN74166J         SN74192N         SN74278N           SN74166N         SN74193J         SN74279J           SN74167J         SN74193N         SN74279N           SN74167N         SN74194J         SN7427J           SN7416J         SN74194N         SN7427N           SN7416J         SN74195J         SN74283J           SN7416N         SN74195J         SN74283J           SN74170J         SN74195N         SN74283N           SN74170N         SN74196J         SN74284J           SN74172J         SN74196N         SN74284N           SN74172N         SN74197J         SN74285J           SN74173J         SN74197N         SN74285N           SN74174J         SN74198N         SN7428N	SN74165J	SN74191N	SN74276N
SN74166N         SN74193J         SN74279J           SN74167J         SN74193N         SN74279N           SN74167N         SN74194J         SN7427J           SN7416J         SN74194N         SN7427N           SN7416J         SN74194N         SN7427N           SN7416N         SN74195J         SN74283J           SN74170J         SN74195N         SN74283N           SN74170N         SN74196J         SN74284J           SN74172J         SN74196N         SN74284N           SN74172N         SN74197J         SN74285J           SN74173J         SN74197N         SN74285N           SN74173N         SN74198J         SN7428N           SN74174J         SN74198N         SN7428N	SN74165N	SN74192J	SN74278J
SN74167J         SN74193N         SN74279N           SN74167N         SN74194J         SN7427J           SN7416J         SN74194N         SN7427N           SN7416N         SN74195J         SN74283J           SN74170J         SN74195N         SN74283N           SN74170N         SN74196J         SN74284J           SN74172J         SN74196N         SN74284N           SN74172N         SN74197J         SN74285J           SN74173J         SN74197N         SN74285N           SN74173N         SN74198J         SN7428J           SN74174J         SN74198N         SN7428N	SN74166J	SN74192N	SN74278N
SN74167N         SN74194J         SN7427J           SN7416J         SN74194N         SN7427N           SN7416N         SN74195J         SN74283J           SN74170J         SN74195N         SN74283N           SN74170N         SN74196J         SN74284J           SN74172J         SN74196N         SN74284N           SN74172N         SN74197J         SN74285J           SN74173J         SN74197N         SN74285N           SN74173N         SN74198J         SN7428N           SN74174J         SN74198N         SN7428N	SN74166N	SN74193J	SN74279J
SN7416J         SN74194N         SN7427N           SN7416N         SN74195J         SN74283J           SN74170J         SN74195N         SN74283N           SN74170N         SN74196J         SN74284J           SN74172J         SN74196N         SN74284N           SN74172N         SN74197J         SN74285J           SN74173J         SN74197N         SN74285N           SN74173N         SN74198J         SN7428J           SN74174J         SN74198N         SN7428N	SN74167J	SN74193N	SN74279N
SN7416N         SN74195J         SN74283J           SN74170J         SN74195N         SN74283N           SN74170N         SN74196J         SN74284J           SN74172J         SN74196N         SN74284N           SN74172N         SN74197J         SN74285J           SN74173J         SN74197N         SN74285N           SN74173N         SN74198J         SN7428J           SN74174J         SN74198N         SN7428N	SN74167N	SN74194J	SN7427J
SN74170J         SN74195N         SN74283N           SN74170N         SN74196J         SN74284J           SN74172J         SN74196N         SN74284N           SN74172N         SN74197J         SN74285J           SN74173J         SN74197N         SN74285N           SN74173N         SN74198J         SN7428J           SN74174J         SN74198N         SN7428N	SN7416J	SN74194N	SN7427N
SN74170N         SN74196J         SN74284J           SN74172J         SN74196N         SN74284N           SN74172N         SN74197J         SN74285J           SN74173J         SN74197N         SN74285N           SN74173N         SN74198J         SN7428J           SN74174J         SN74198N         SN7428N	SN7416N	SN74195J	SN74283J
SN74172J         SN74196N         SN74284N           SN74172N         SN74197J         SN74285J           SN74173J         SN74197N         SN74285N           SN74173N         SN74198J         SN7428J           SN74174J         SN74198N         SN7428N	SN74170J	SN74195N	SN74283N
SN74172N       SN74197J       SN74285J         SN74173J       SN74197N       SN74285N         SN74173N       SN74198J       SN7428J         SN74174J       SN74198N       SN7428N	SN74170N	SN74196J	SN74284J
SN74173J         SN74197N         SN74285N           SN74173N         SN74198J         SN7428J           SN74174J         SN74198N         SN7428N	SN74172J	SN74196N	SN74284N
SN74173N         SN74198J         SN7428J           SN74174J         SN74198N         SN7428N	SN74172N	SN74197J	SN74285J
SN74174J SN74198N SN7428N	SN74173J	SN74197N	SN74285N
, , , , , , , , , , , , , , , , , , ,	SN74173N	SN74198J	SN7428J
SN74174N SN74199J SN74290J	SN74174J	SN74198N	SN7428N
	SN74174N	SN74199J	SN74290J

Appendix A: Digital Integrated Circuits included in P-CAD Signal Integrity

SN74175J	SN74199N	SN74290N
SN74175N	SN7420J	SN74293J
SN74176J	SN7420N	SN74293N
SN74176N	SN74221J	SN74298J
SN74177J	SN74221N	SN74298N
SN74177N	SN7422J	SN7430J
SN74178J	SN7422N	SN7430N
SN74178N	SN7423J	SN7432J
SN74179J	SN7423N	SN7432N
SN74179N	SN74247J	SN7433J
SN7417J	SN74247N	SN7433N
SN7417N	SN74251J	SN74365AJ
SN74180J	SN74251N	SN74365AN
SN74180N	SN74259J	SN74366AJ
SN74366AN	SN7454N	SN74ABT162240DGG
SN74367AJ	SN7470J	SN74ABT162240DL
SN74367AN	SN7470N	SN74ABT162244DGG
SN74368AJ	SN7472J	SN74ABT162244DL
SN74368AN	SN7472N	SN74ABT162245DGG
SN74376J	SN7473J	SN74ABT162245DL
SN74376N	SN7473N	SN74ABT162260DL
SN7437J	SN7474J	SN74ABT16240DGG
SN7437N	SN7474N	SN74ABT16240DL
SN7438J	SN7475J	SN74ABT16241DGG
SN7438N	SN7475N	SN74ABT16241DL
SN74390J	SN7476J	SN74ABT16244DGG
SN74390N	SN7476N	SN74ABT16244DL
SN74393J	SN7482J	SN74ABT16245DGG
SN74393N	SN7482N	SN74ABT16245DL
SN7439J	SN7483AJ	SN74ABT162500DGG
SN7439N	SN7483AN	SN74ABT162500DL
SN7440J	SN7485J	SN74ABT162501DGG
SN7440N	SN7485N	SN74ABT162501DL

Appendix A: Digital Integrated Circuits included in P-CAD Signal Integrity

SN74425J	SN7486J	SN74ABT162600DGG
SN74425N	SN7486N	SN74ABT162600DL
SN7442AJ	SN7490AJ	SN74ABT162601DGG
SN7442AN	SN7490AN	SN74ABT162601DL
SN7445J	SN7492AJ	SN74ABT16260DL
SN7445N	SN7492AN	SN74ABT16373DGG
SN7446AJ	SN7493AJ	SN74ABT16373DL
SN7446AN	SN7493AN	SN74ABT16374DGG
SN7447AJ	SN7495AJ	SN74ABT16374DL
SN7447AN	SN7495AN	SN74ABT16377DGG
SN7448J	SN7496J	SN74ABT16377DL
SN7448N	SN7496N	SN74ABT16460DGG
SN74490J	SN7497J	SN74ABT16460DL
SN74490N	SN7497N	SN74ABT16470DGG
SN7450J	SN74ABT125D	SN74ABT16470DL
SN7450N	SN74ABT125DB	SN74ABT16500ADGG
SN7451J	SN74ABT125N	SN74ABT16500ADL
SN7451N	SN74ABT125PW	SN74ABT16501DGG
SN7453J	SN74ABT126D	SN74ABT16501DL
SN7453N	SN74ABT126DB	SN74ABT16540DGG
SN7454J	SN74ABT126N	SN74ABT16540DL
SN74ABT16541DGG	SN74ABT2240DB	SN74ABT273PW
SN74ABT16541DL	SN74ABT2240DW	SN74ABT2952ADB
SN74ABT16543DGG	SN74ABT2240N	SN74ABT2952ADW
SN74ABT16543DL	SN74ABT2240PW	SN74ABT2952ANT
SN74ABT16600DGG	SN74ABT2241DB	SN74ABT2952APW
SN74ABT16600DL	SN74ABT2241DW	SN74ABT2953DB
SN74ABT16601DGG	SN74ABT2241N	SN74ABT2953DW
SN74ABT16601DL	SN74ABT2241PW	SN74ABT2953NT
SN74ABT16623DGG	SN74ABT2244DB	SN74ABT2953PW
SN74ABT16623DL	SN74ABT2244DW	SN74ABT32245PZ
SN74ABT16640DGG	SN74ABT2244N	SN74ABT32316PN
SN74ABT16640DL	SN74ABT2244PW	SN74ABT32318PN

Appendix A: Digital Integrated Circuits included in P-CAD Signal Integrity

SN74ABT16646DGG	SN74ABT2245DB	SN74ABT32373PZ
SN74ABT16646DL	SN74ABT2245DW	SN74ABT32374PZ
SN74ABT16648DGG	SN74ABT2245N	SN74ABT32500PZ
SN74ABT16648DL	SN74ABT240DB	SN74ABT32501PZ
SN74ABT16651DL	SN74ABT240DW	SN74ABT32543PZ
SN74ABT16652DL	SN74ABT240N	SN74ABT32952PZ
SN74ABT16657DGG	SN74ABT240PW	SN74ABT373DB
SN74ABT16657DL	SN74ABT241DB	SN74ABT373DW
SN74ABT16821DGG	SN74ABT241DW	SN74ABT373N
SN74ABT16821DL	SN74ABT241N	SN74ABT373PW
SN74ABT16823DGG	SN74ABT241PW	SN74ABT374DB
SN74ABT16823DL	SN74ABT244DB	SN74ABT374DW
SN74ABT16825DGG	SN74ABT244DW	SN74ABT374N
SN74ABT16825DL	SN74ABT244N	SN74ABT374PW
SN74ABT16826DGG	SN74ABT244PW	SN74ABT377DB
SN74ABT16826DL	SN74ABT245DB	SN74ABT377DW
SN74ABT16827DL	SN74ABT245DW	SN74ABT377N
SN74ABT16828DL	SN74ABT245N	SN74ABT377PW
SN74ABT16833DGG	SN74ABT245PW	SN74ABT533DB
SN74ABT16833DL	SN74ABT25241DW	SN74ABT533DW
SN74ABT16841DL	SN74ABT25241NT	SN74ABT533N
SN74ABT16843DGG	SN74ABT25244DW	SN74ABT533PW
SN74ABT16843DL	SN74ABT25244NT	SN74ABT534DB
SN74ABT16853DL	SN74ABT25245DW	SN74ABT534DW
SN74ABT16862DL	SN74ABT25245NT	SN74ABT534N
SN74ABT16863DL	SN74ABT273DB	SN74ABT534PW
SN74ABT16952DGG	SN74ABT273DW	SN74ABT5400DW
SN74ABT16952DL	SN74ABT273N	SN74ABT5401DW
SN74ABT5402DW	SN74ABT646APW	SN74ABT853NT
SN74ABT5403DW	SN74ABT651DB	SN74ABT853PW
SN74ABT540DB	SN74ABT651DW	SN74ABT861DB
SN74ABT540DW	SN74ABT651NT	SN74ABT861DW
SN74ABT540N	SN74ABT651PW	SN74ABT861NT

Appendix A: Digital Integrated Circuits included in P-CAD Signal Integrity

		1
SN74ABT541DB	SN74ABT652ADB	SN74ABT862DB
SN74ABT541DW	SN74ABT652ADW	SN74ABT862DW
SN74ABT541N	SN74ABT652ANT	SN74ABT862NT
SN74ABT541PW	SN74ABT652APW	SN74ABT863DB
SN74ABT543DB	SN74ABT657DB	SN74ABT863DW
SN74ABT543DW	SN74ABT657DW	SN74ABT863NT
SN74ABT543NT	SN74ABT657NT	SN74AC00D
SN74ABT543PW	SN74ABT821DB	SN74AC00DB
SN74ABT544DB	SN74ABT821DW	SN74AC00N
SN74ABT544DW	SN74ABT821NT	SN74AC00PW
SN74ABT544NT	SN74ABT821PW	SN74AC04D
SN74ABT544PW	SN74ABT823DB	SN74AC04DB
SN74ABT573DB	SN74ABT823DW	SN74AC04N
SN74ABT573DW	SN74ABT823NT	SN74AC04PW
SN74ABT573N	SN74ABT823PW	SN74AC08D
SN74ABT573PW	SN74ABT827DB	SN74AC08DB
SN74ABT574DB	SN74ABT827DW	SN74AC08N
SN74ABT574DW	SN74ABT827NT	SN74AC08PW
SN74ABT574N	SN74ABT827PW	SN74AC10D
SN74ABT574PW	SN74ABT828DB	SN74AC10DB
SN74ABT620DB	SN74ABT828DW	SN74AC10N
SN74ABT620DW	SN74ABT828NT	SN74AC10PW
SN74ABT620N	SN74ABT828PW	SN74AC11000D
SN74ABT620PW	SN74ABT833DB	SN74AC11000N
SN74ABT623DB	SN74ABT833DW	SN74AC11002D
SN74ABT623DW	SN74ABT833NT	SN74AC11002N
SN74ABT623N	SN74ABT841DB	SN74AC11004DB
SN74ABT623PW	SN74ABT841DW	SN74AC11004DW
SN74ABT640DB	SN74ABT841NT	SN74AC11004N
SN74ABT640DW	SN74ABT841PW	SN74AC11008D
SN74ABT640N	SN74ABT843DB	SN74AC11008N
SN74ABT640PW	SN74ABT843DW	SN74AC11010D
SN74ABT646ADB	SN74ABT843NT	SN74AC11010N
	-	

Appendix A: Digital Integrated Circuits included in P-CAD Signal Integrity

SN74ABT646ADW	SN74ABT853DB	SN74AC11011D
SN74ABT646ANT	SN74ABT853DW	SN74AC11011N
SN74AC11014DW	SN74AC11174DW	SN74AC11520N
SN74AC11014N	SN74AC11174N	SN74AC11521DB
SN74AC11020D	SN74AC11175DW	SN74AC11521DW
SN74AC11020N	SN74AC11175N	SN74AC11521N
SN74AC11021D	SN74AC11181DW	SN74AC11533DW
SN74AC11021N	SN74AC11238D	SN74AC11533NT
SN74AC11027D	SN74AC11238N	SN74AC11534DW
SN74AC11027N	SN74AC11240DB	SN74AC11534NT
SN74AC11030D	SN74AC11240DW	SN74AC11590DW
SN74AC11030N	SN74AC11240NT	SN74AC11590N
SN74AC11032D	SN74AC11241DB	SN74AC11593DW
SN74AC11032DB	SN74AC11241DW	SN74AC11593NT
SN74AC11032N	SN74AC11241NT	SN74AC11646DW
SN74AC11034DW	SN74AC11244DB	SN74AC11648DW
SN74AC11034N	SN74AC11244DW	SN74AC11648NT
SN74AC11074D	SN74AC11244NT	SN74AC11652DW
SN74AC11074N	SN74AC11244PW	SN74AC11652NT
SN74AC11074PW	SN74AC11245DB	SN74AC11800DW
SN74AC11086D	SN74AC11245DW	SN74AC11827DW
SN74AC11086N	SN74AC11245NT	SN74AC11873DW
SN74AC11109D	SN74AC11245PW	SN74AC11898DW
SN74AC11109N	SN74AC11253D	SN74AC11898N
SN74AC11112D	SN74AC11253N	SN74AC11D
SN74AC11112N	SN74AC11257DW	SN74AC11DB
SN74AC11132D	SN74AC11257N	SN74AC11N
SN74AC11132N	SN74AC11273DW	SN74AC11PW
SN74AC11138D	SN74AC11273NT	SN74AC14AD
SN74AC11138N	SN74AC11280D	SN74AC14ADB
SN74AC11138PW	SN74AC11280N	SN74AC14AN
SN74AC11139D	SN74AC11286D	SN74AC14APW
SN74AC11139N	SN74AC11286N	SN74AC16240DL

Appendix A: Digital Integrated Circuits included in P-CAD Signal Integrity

SN74AC11139PW	SN74AC11373DB	SN74AC16244DGG
SN74AC11151D	SN74AC11373DW	SN74AC16244DL
SN74AC11151N	SN74AC11373NT	SN74AC16245DGG
SN74AC11153D	SN74AC11374DB	SN74AC16245DL
SN74AC11153N	SN74AC11374DW	SN74AC16373DL
SN74AC11157DW	SN74AC11374NT	SN74AC16374DL
SN74AC11157N	SN74AC11377DW	SN74AC16472DL
SN74AC11158DW	SN74AC11377NT	SN74AC16543DL
SN74AC11158N	SN74AC11520DW	SN74AC16620DL
SN74AC16623DL	SN74AC534PW	SN74ACT10PW
SN74AC16640DL	SN74AC563DB	SN74ACT11000D
SN74AC16646DL	SN74AC563DW	SN74ACT11000N
SN74AC16652DL	SN74AC563N	SN74ACT11002D
SN74AC16823DL	SN74AC563PW	SN74ACT11002N
SN74AC240DB	SN74AC564DB	SN74ACT11004DB
SN74AC240DW	SN74AC564DW	SN74ACT11004DW
SN74AC240N	SN74AC564N	SN74ACT11004N
SN74AC240PW	SN74AC564PW	SN74ACT11008D
SN74AC241DB	SN74AC573DB	SN74ACT11008N
SN74AC241DW	SN74AC573DW	SN74ACT11008PW
SN74AC241N	SN74AC573N	SN74ACT11010D
SN74AC241PW	SN74AC573PW	SN74ACT11010N
SN74AC244DB	SN74AC574DB	SN74ACT11011D
SN74AC244DW	SN74AC574DW	SN74ACT11011N
SN74AC244N	SN74AC574N	SN74ACT11014DW
SN74AC244PW	SN74AC574PW	SN74ACT11014N
SN74AC245DB	SN74AC74D	SN74ACT11020D
SN74AC245DW	SN74AC74DB	SN74ACT11020N
SN74AC245N	SN74AC74N	SN74ACT11021D
SN74AC245PW	SN74AC74PW	SN74ACT11021N
SN74AC32D	SN74AC86D	SN74ACT11027D
SN74AC32DB	SN74AC86DB	SN74ACT11027N
SN74AC32N	SN74AC86N	SN74ACT11030D
	•	-

Appendix A: Digital Integrated Circuits included in P-CAD Signal Integrity

SN74AC32PW	SN74AC86PW	SN74ACT11030N
SN74AC373DB	SN74ACT00D	SN74ACT11032D
SN74AC373DW	SN74ACT00DB	SN74ACT11032DB
SN74AC373N	SN74ACT00N	SN74ACT11032N
SN74AC373PW	SN74ACT00PW	SN74ACT11032PW
SN74AC374DB	SN74ACT04D	SN74ACT11034DW
SN74AC374DW	SN74ACT04DB	SN74ACT11034N
SN74AC374N	SN74ACT04N	SN74ACT11074D
SN74AC374PW	SN74ACT04PW	SN74ACT11074DB
SN74AC533DB	SN74ACT08D	SN74ACT11074N
SN74AC533DW	SN74ACT08DB	SN74ACT11086D
SN74AC533N	SN74ACT08N	SN74ACT11086N
SN74AC533PW	SN74ACT08PW	SN74ACT11109D
SN74AC534DB	SN74ACT10D	SN74ACT11109N
SN74AC534DW	SN74ACT10DB	SN74ACT11112D
SN74AC534N	SN74ACT10N	SN74ACT11112N
SN74ACT11132D	SN74ACT11245PW	SN74ACT11623DW
SN74ACT11132N	SN74ACT11253D	SN74ACT11623NT
SN74ACT11138D	SN74ACT11253N	SN74ACT11640DW
SN74ACT11138N	SN74ACT11257DW	SN74ACT11640NT
SN74ACT11138PW	SN74ACT11257N	SN74ACT11646DW
SN74ACT11139D	SN74ACT11258DW	SN74ACT11648DW
SN74ACT11139N	SN74ACT11258N	SN74ACT11652DW
SN74ACT11139PW	SN74ACT11273DW	SN74ACT11652NT
SN74ACT11151D	SN74ACT11273NT	SN74ACT11657DW
SN74ACT11151N	SN74ACT11280D	SN74ACT11802DW
SN74ACT11153D	SN74ACT11280N	SN74ACT11802NT
SN74ACT11153N	SN74ACT11286D	SN74ACT11821DW
SN74ACT11157DW	SN74ACT11286N	SN74ACT11825DW
SN74ACT11157N	SN74ACT11353D	SN74ACT11827DW
SN74ACT11158DW	SN74ACT11353N	SN74ACT11828DW
SN74ACT11158N	SN74ACT11373DB	SN74ACT11867DW
SN74ACT11174DW	SN74ACT11373DW	SN74ACT11874DW

Appendix A: Digital Integrated Circuits included in P-CAD Signal Integrity

SN74ACT11174N	SN74ACT11373NT	SN74ACT11898DW
SN74ACT11175DW	SN74ACT11374DB	SN74ACT11898N
SN74ACT11175N	SN74ACT11374DW	SN74ACT11D
SN74ACT11181DW	SN74ACT11374NT	SN74ACT11DB
SN74ACT11191DW	SN74ACT11377DB	SN74ACT11N
SN74ACT11191N	SN74ACT11377DW	SN74ACT11PW
SN74ACT11194DW	SN74ACT11377NT	SN74ACT14AD
SN74ACT11194N	SN74ACT11470DW	SN74ACT14ADB
SN74ACT11238D	SN74ACT11520DW	SN74ACT14AN
SN74ACT11238N	SN74ACT11520N	SN74ACT14APW
SN74ACT11240DB	SN74ACT11521DB	SN74ACT16240DL
SN74ACT11240DW	SN74ACT11521DW	SN74ACT16241DL
SN74ACT11240NT	SN74ACT11521N	SN74ACT16244DGG
SN74ACT11241DB	SN74ACT11533DW	SN74ACT16244DL
SN74ACT11241DW	SN74ACT11533NT	SN74ACT16245DGG
SN74ACT11241NT	SN74ACT11534DW	SN74ACT16245DL
SN74ACT11244DB	SN74ACT11534NT	SN74ACT16373DL
SN74ACT11244DW	SN74ACT11543DW	SN74ACT16374DL
SN74ACT11244NT	SN74ACT11544DW	SN74ACT16470DL
SN74ACT11244PW	SN74ACT11590DW	SN74ACT16474DL
SN74ACT11245DB	SN74ACT11590N	SN74ACT16475DL
SN74ACT11245DW	SN74ACT11593DW	SN74ACT16540DL
SN74ACT11245NT	SN74ACT11593NT	SN74ACT16541DL
SN74ACT16543DL	SN74ACT373DB	SN74AHC00DB
SN74ACT16544DL	SN74ACT373DW	SN74AHC00N
SN74ACT16620DL	SN74ACT373N	SN74AHC00PW
SN74ACT16623DL	SN74ACT373PW	SN74AHC02D
SN74ACT16640DL	SN74ACT374DB	SN74AHC02DB
SN74ACT16646DL	SN74ACT374DW	SN74AHC02N
SN74ACT16648DL	SN74ACT374N	SN74AHC02PW
SN74ACT16651DL	SN74ACT374PW	SN74AHC04D
SN74ACT16652DL	SN74ACT533DB	SN74AHC04DB
SN74ACT16657DL	SN74ACT533DW	SN74AHC04N

Appendix A: Digital Integrated Circuits included in P-CAD Signal Integrity

		1
SN74ACT16821DL	SN74ACT533N	SN74AHC04PW
SN74ACT16823DL	SN74ACT533PW	SN74AHC08D
SN74ACT16825DL	SN74ACT534DB	SN74AHC08DB
SN74ACT16827DL	SN74ACT534DW	SN74AHC08N
SN74ACT16833DL	SN74ACT534N	SN74AHC08PW
SN74ACT16841DL	SN74ACT563DB	SN74AHC125D
SN74ACT16861DL	SN74ACT563DW	SN74AHC125DB
SN74ACT16863DL	SN74ACT563N	SN74AHC125N
SN74ACT16864DL	SN74ACT563PW	SN74AHC125PW
SN74ACT16952DL	SN74ACT564DB	SN74AHC126D
SN74ACT240DB	SN74ACT564DW	SN74AHC126DB
SN74ACT240DW	SN74ACT564N	SN74AHC126N
SN74ACT240N	SN74ACT564PW	SN74AHC126PW
SN74ACT240PW	SN74ACT573DB	SN74AHC138D
SN74ACT241DB	SN74ACT573DW	SN74AHC138DB
SN74ACT241DW	SN74ACT573N	SN74AHC138N
SN74ACT241N	SN74ACT573PW	SN74AHC138PW
SN74ACT241PW	SN74ACT574DB	SN74AHC139D
SN74ACT244DB	SN74ACT574DW	SN74AHC139DB
SN74ACT244DW	SN74ACT574N	SN74AHC139N
SN74ACT244N	SN74ACT574PW	SN74AHC139PW
SN74ACT244PW	SN74ACT74D	SN74AHC14D
SN74ACT245DB	SN74ACT74DB	SN74AHC14DB
SN74ACT245DW	SN74ACT74N	SN74AHC14N
SN74ACT245N	SN74ACT74PW	SN74AHC14PW
SN74ACT245PW	SN74ACT86D	SN74AHC240DB
SN74ACT32D	SN74ACT86DB	SN74AHC240DW
SN74ACT32DB	SN74ACT86N	SN74AHC240N
SN74ACT32N	SN74ACT86PW	SN74AHC240PW
SN74ACT32PW	SN74AHC00D	SN74AHC244DB
SN74AHC244DW	SN74AHC86DB	SN74AHCT240DW
SN74AHC244N	SN74AHC86N	SN74AHCT240N
SN74AHC244PW	SN74AHC86PW	SN74AHCT240PW

Appendix A: Digital Integrated Circuits included in P-CAD Signal Integrity

SN74AHC245DB	SN74AHCT00D	SN74AHCT244DB
SN74AHC245DW	SN74AHCT00DB	SN74AHCT244DW
SN74AHC245N	SN74AHCT00N	SN74AHCT244N
SN74AHC245PW	SN74AHCT00PW	SN74AHCT244PW
SN74AHC32D	SN74AHCT02D	SN74AHCT245DB
SN74AHC32DB	SN74AHCT02DB	SN74AHCT245DW
SN74AHC32N	SN74AHCT02N	SN74AHCT245N
SN74AHC32PW	SN74AHCT02PW	SN74AHCT245PW
SN74AHC373DB	SN74AHCT04D	SN74AHCT32D
SN74AHC373DW	SN74AHCT04DB	SN74AHCT32DB
SN74AHC373N	SN74AHCT04N	SN74AHCT32N
SN74AHC373PW	SN74AHCT04PW	SN74AHCT32PW
SN74AHC374DB	SN74AHCT08D	SN74AHCT373DB
SN74AHC374DW	SN74AHCT08DB	SN74AHCT373DW
SN74AHC374N	SN74AHCT08N	SN74AHCT373N
SN74AHC374PW	SN74AHCT08PW	SN74AHCT373PW
SN74AHC540DB	SN74AHCT125D	SN74AHCT374DB
SN74AHC540DW	SN74AHCT125DB	SN74AHCT374DW
SN74AHC540N	SN74AHCT125N	SN74AHCT374N
SN74AHC540PW	SN74AHCT125PW	SN74AHCT374PW
SN74AHC541DB	SN74AHCT126D	SN74AHCT540DB
SN74AHC541DW	SN74AHCT126DB	SN74AHCT540DW
SN74AHC541N	SN74AHCT126N	SN74AHCT540N
SN74AHC541PW	SN74AHCT126PW	SN74AHCT540PW
SN74AHC573DB	SN74AHCT138D	SN74AHCT541DB
SN74AHC573DW	SN74AHCT138DB	SN74AHCT541DW
SN74AHC573N	SN74AHCT138N	SN74AHCT541N
SN74AHC573PW	SN74AHCT138PW	SN74AHCT541PW
SN74AHC574DB	SN74AHCT139D	SN74AHCT573DB
SN74AHC574DW	SN74AHCT139DB	SN74AHCT573DW
SN74AHC574N	SN74AHCT139N	SN74AHCT573N
SN74AHC574PW	SN74AHCT139PW	SN74AHCT573PW
SN74AHC74D	SN74AHCT14D	SN74AHCT574DB
		-

Appendix A: Digital Integrated Circuits included in P-CAD Signal Integrity

SN74AHC74DB	SN74AHCT14DB	SN74AHCT574DW
SN74AHC74N	SN74AHCT14N	SN74AHCT574N
SN74AHC74PW	SN74AHCT14PW	SN74AHCT574PW
SN74AHC86D	SN74AHCT240DB	SN74AHCT74D
SN74AHCT74DB	SN74ALS1010AD	SN74ALS139D
SN74AHCT74N	SN74ALS1010AN	SN74ALS139N
SN74AHCT74PW	SN74ALS1020AD	SN74ALS151D
SN74AHCT86D	SN74ALS1020AN	SN74ALS151N
SN74AHCT86DB	SN74ALS1032AD	SN74ALS153D
SN74AHCT86N	SN74ALS1032AN	SN74ALS153N
SN74AHCT86PW	SN74ALS1034D	SN74ALS154DW
SN74AHCU04D	SN74ALS1034N	SN74ALS154NT
SN74AHCU04DB	SN74ALS1035D	SN74ALS156D
SN74AHCU04N	SN74ALS1035N	SN74ALS156N
SN74AHCU04PW	SN74ALS109AD	SN74ALS157AD
SN74ALS00AD	SN74ALS109AN	SN74ALS157AN
SN74ALS00AN	SN74ALS10AD	SN74ALS158D
SN74ALS01D	SN74ALS10AN	SN74ALS158N
SN74ALS01N	SN74ALS112AD	SN74ALS15AD
SN74ALS02D	SN74ALS112AN	SN74ALS15AN
SN74ALS02N	SN74ALS113AD	SN74ALS160BD
SN74ALS03BD	SN74ALS113AN	SN74ALS160BN
SN74ALS03BN	SN74ALS114AD	SN74ALS161BD
SN74ALS04BD	SN74ALS114AN	SN74ALS161BN
SN74ALS04BDB	SN74ALS11AD	SN74ALS162BD
SN74ALS04BN	SN74ALS11AN	SN74ALS162BN
SN74ALS05AD	SN74ALS1240-1DW	SN74ALS163BD
SN74ALS05AN	SN74ALS1240-1N	SN74ALS163BN
SN74ALS08D	SN74ALS1244-1ADW	SN74ALS1640-1ADW
SN74ALS08N	SN74ALS1244-1AN	SN74ALS1640-1AN
SN74ALS09D	SN74ALS1245-1ADW	SN74ALS1645-1ADW
SN74ALS09N	SN74ALS1245-1AN	SN74ALS1645-1AN
SN74ALS1000AD	SN74ALS12AD	SN74ALS164AD

Appendix A: Digital Integrated Circuits included in P-CAD Signal Integrity

SN74ALS1000AN	SN74ALS12AN	SN74ALS164AN
SN74ALS1002AD	SN74ALS131D	SN74ALS165D
SN74ALS1002AN	SN74ALS131N	SN74ALS165N
SN74ALS1003AD	SN74ALS133D	SN74ALS166D
SN74ALS1003AN	SN74ALS133N	SN74ALS166N
SN74ALS1004D	SN74ALS136D	SN74ALS168BD
SN74ALS1004N	SN74ALS136N	SN74ALS168BN
SN74ALS1005D	SN74ALS137AD	SN74ALS169BD
SN74ALS1005N	SN74ALS137AN	SN74ALS169BN
SN74ALS1008AD	SN74ALS138AD	SN74ALS174D
SN74ALS1008AN	SN74ALS138AN	SN74ALS174N
SN74ALS175D	SN74ALS235N	SN74ALS29821DW
SN74ALS175N	SN74ALS236DW	SN74ALS29821NT
SN74ALS1804ADW	SN74ALS236N	SN74ALS29822DW
SN74ALS1804AN	SN74ALS240ADW	SN74ALS29822NT
SN74ALS190D	SN74ALS240AN	SN74ALS29823DW
SN74ALS190N	SN74ALS241CD	SN74ALS29823NT
SN74ALS191AD	SN74ALS241CN	SN74ALS29824DW
SN74ALS191AN	SN74ALS242BD	SN74ALS29824NT
SN74ALS192D	SN74ALS242BN	SN74ALS29825DW
SN74ALS192N	SN74ALS243AD	SN74ALS29825NT
SN74ALS193AD	SN74ALS243AN	SN74ALS29826DW
SN74ALS193AN	SN74ALS244CDW	SN74ALS29826NT
SN74ALS194D	SN74ALS244CN	SN74ALS29827DW
SN74ALS194N	SN74ALS245ABD	SN74ALS29827NT
SN74ALS20AD	SN74ALS245ADW	SN74ALS29828DW
SN74ALS20AN	SN74ALS245AN	SN74ALS29828NT
SN74ALS21AD	SN74ALS251D	SN74ALS29833DW
SN74ALS21AN	SN74ALS251N	SN74ALS29833NT
SN74ALS2232ANT	SN74ALS253D	SN74ALS29841DW
SN74ALS2233ANT	SN74ALS253N	SN74ALS29841NT
SN74ALS2238N	SN74ALS2540DW	SN74ALS29842DW
SN74ALS2239D	SN74ALS2540N	SN74ALS29842NT

Appendix A: Digital Integrated Circuits included in P-CAD Signal Integrity

SN74ALS2239N	SN74ALS2541DW	SN74ALS29843DW
SN74ALS2240DW	SN74ALS2541N	SN74ALS29843NT
SN74ALS2240N	SN74ALS257AD	SN74ALS29844DW
SN74ALS2241DW	SN74ALS257AN	SN74ALS29844NT
SN74ALS2241N	SN74ALS258AD	SN74ALS29845DW
SN74ALS2244DW	SN74ALS258AN	SN74ALS29845NT
SN74ALS2244N	SN74ALS259D	SN74ALS29846DW
SN74ALS229BDW	SN74ALS259N	SN74ALS29846NT
SN74ALS229BN	SN74ALS273DW	SN74ALS29853DW
SN74ALS22BD	SN74ALS273N	SN74ALS29853NT
SN74ALS22BN	SN74ALS27AD	SN74ALS29854DW
SN74ALS232BDW	SN74ALS27AN	SN74ALS29854NT
SN74ALS232BN	SN74ALS280D	SN74ALS29861DW
SN74ALS233BDW	SN74ALS280N	SN74ALS29861NT
SN74ALS233BN	SN74ALS28AD	SN74ALS29862DW
SN74ALS234DW	SN74ALS28AN	SN74ALS29862NT
SN74ALS234N	SN74ALS29818DW	SN74ALS29863DW
SN74ALS235DW	SN74ALS29818NT	SN74ALS29863NT
SN74ALS29864DW	SN74ALS521DW	SN74ALS577AN
SN74ALS29864NT	SN74ALS521N	SN74ALS580BDW
SN74ALS299DW	SN74ALS522DW	SN74ALS580BN
SN74ALS299N	SN74ALS522N	SN74ALS620ADW
SN74ALS30AD	SN74ALS526DW	SN74ALS620AN
SN74ALS30AN	SN74ALS526N	SN74ALS621ADW
SN74ALS323DW	SN74ALS527DW	SN74ALS621AN
SN74ALS323N	SN74ALS527N	SN74ALS622ADW
SN74ALS32AD	SN74ALS528DW	SN74ALS622AN
SN74ALS32AN	SN74ALS528N	SN74ALS623ADW
SN74ALS33AD	SN74ALS533ADW	SN74ALS623AN
SN74ALS33AN	SN74ALS533AN	SN74ALS638ADW
SN74ALS34D	SN74ALS534ADW	SN74ALS638AN
SN74ALS34N	SN74ALS534AN	SN74ALS639ADW
SN74ALS352D	SN74ALS540DW	SN74ALS639AN

Appendix A: Digital Integrated Circuits included in P-CAD Signal Integrity

SN74ALS352N	SN74ALS540N	SN74ALS640BDW
SN74ALS353D	SN74ALS541DW	SN74ALS640BN
SN74ALS353N	SN74ALS541N	SN74ALS641ADW
SN74ALS35AD	SN74ALS560ADW	SN74ALS641AN
SN74ALS35AN	SN74ALS560AN	SN74ALS642ADW
SN74ALS373ADW	SN74ALS561ADW	SN74ALS642AN
SN74ALS373AN	SN74ALS561AN	SN74ALS643ADW
SN74ALS374ADW	SN74ALS563BDW	SN74ALS643AN
SN74ALS374AN	SN74ALS563BN	SN74ALS645ADW
SN74ALS37AD	SN74ALS564BDW	SN74ALS645AN
SN74ALS37AN	SN74ALS564BN	SN74ALS646ADW
SN74ALS38BD	SN74ALS568ADW	SN74ALS646ANT
SN74ALS38BN	SN74ALS568AN	SN74ALS647DW
SN74ALS40AD	SN74ALS569ADW	SN74ALS647NT
SN74ALS40AN	SN74ALS569AN	SN74ALS648ADW
SN74ALS465ADW	SN74ALS573CDB	SN74ALS648ANT
SN74ALS465AN	SN74ALS573CDW	SN74ALS651ADW
SN74ALS466ADW	SN74ALS573CN	SN74ALS651ANT
SN74ALS466AN	SN74ALS574BDW	SN74ALS652ADW
SN74ALS518DW	SN74ALS574BN	SN74ALS652ANT
SN74ALS518N	SN74ALS575ADW	SN74ALS653DW
SN74ALS519DW	SN74ALS575AN	SN74ALS653NT
SN74ALS519N	SN74ALS576BDW	SN74ALS654DW
SN74ALS520DW	SN74ALS576BN	SN74ALS654NT
SN74ALS520N	SN74ALS577ADW	SN74ALS666DW
SN74ALS666NT	SN74ALS810N	SN74ALS994DW
SN74ALS667DW	SN74ALS811D	SN74ALS994NT
SN74ALS667NT	SN74ALS811N	SN74ALS996DW
SN74ALS677ADW	SN74ALS8169N	SN74ALS996NT
SN74ALS677ANT	SN74ALS832ADW	SN74ALVC16240DGG
SN74ALS678DW	SN74ALS832AN	SN74ALVC16240DL
SN74ALS678NT	SN74ALS857DW	SN74ALVC16244DGG
SN74ALS679DW	SN74ALS857NT	SN74ALVC16244DL

Appendix A: Digital Integrated Circuits included in P-CAD Signal Integrity

SN74ALS679N	SN74ALS867ADW	SN74ALVC16245DGG
SN74ALS680DW	SN74ALS867ANT	SN74ALVC16245DL
SN74ALS680N	SN74ALS869DW	SN74ALVC16260DGG
SN74ALS688DW	SN74ALS869NT	SN74ALVC16260DL
SN74ALS688N	SN74ALS86D	SN74ALVC16269DGG
SN74ALS689DW	SN74ALS86N	SN74ALVC16269DL
SN74ALS689N	SN74ALS870DW	SN74ALVC16270DGG
SN74ALS746DW	SN74ALS870NT	SN74ALVC16270DL
SN74ALS746N	SN74ALS873BDW	SN74ALVC16271DGG
SN74ALS747DW	SN74ALS873BNT	SN74ALVC16271DL
SN74ALS747N	SN74ALS874BDW	SN74ALVC16272DGG
SN74ALS74AD	SN74ALS874BNT	SN74ALVC16272DL
SN74ALS74AN	SN74ALS876ADW	SN74ALVC16373DGG
SN74ALS756DW	SN74ALS876ANT	SN74ALVC16373DL
SN74ALS756N	SN74ALS878ADW	SN74ALVC16374DGG
SN74ALS757DW	SN74ALS878ANT	SN74ALVC16374DL
SN74ALS757N	SN74ALS879ADW	SN74ALVC164245DGG
SN74ALS758D	SN74ALS879ANT	SN74ALVC164245DL
SN74ALS758N	SN74ALS880ADW	SN74ALVC16500DGG
SN74ALS760DW	SN74ALS880ANT	SN74ALVC16500DL
SN74ALS760N	SN74ALS963DW	SN74ALVC16501DGG
SN74ALS762DW	SN74ALS963N	SN74ALVC16501DL
SN74ALS762N	SN74ALS964DW	SN74ALVC16540DGG
SN74ALS763DW	SN74ALS964N	SN74ALVC16540DL
SN74ALS763N	SN74ALS990DW	SN74ALVC16541DGG
SN74ALS8003AD	SN74ALS990N	SN74ALVC16541DL
SN74ALS8003AP	SN74ALS991DW	SN74ALVC16543DGG
SN74ALS804ADW	SN74ALS991N	SN74ALVC16543DL
SN74ALS804AN	SN74ALS992DW	SN74ALVC16600DGG
SN74ALS805ADW	SN74ALS992NT	SN74ALVC16600DL
SN74ALS805AN	SN74ALS993DW	SN74ALVC16601DGG
SN74ALS810D	SN74ALS993NT	SN74ALVC16601DL
SN74ALVC16646DGG	SN74AS1034AD	SN74AS175AD

Appendix A: Digital Integrated Circuits included in P-CAD Signal Integrity

SN74ALVC16646DL	SN74AS1034AN	SN74AS175AN
SN74ALVC16652DGG	SN74AS1036AD	SN74AS1804DW
SN74ALVC16652DL	SN74AS1036AN	SN74AS1804N
SN74ALVC16721DGG	SN74AS109D	SN74AS1805DW
SN74ALVC16721DL	SN74AS109N	SN74AS1805N
SN74ALVC16820DGG	SN74AS10D	SN74AS1808DW
SN74ALVC16820DL	SN74AS10N	SN74AS1808N
SN74ALVC16821DGG	SN74AS1181DW	SN74AS181ADW
SN74ALVC16821DL	SN74AS1181NT	SN74AS181ANT
SN74ALVC16823DGG	SN74AS11D	SN74AS181ANW
SN74ALVC16823DL	SN74AS11N	SN74AS181BN
SN74ALVC16825DGG	SN74AS131AD	SN74AS181BNT
SN74ALVC16825DL	SN74AS131AN	SN74AS1821NT
SN74ALVC16827DGG	SN74AS136D	SN74AS1832N
SN74ALVC16827DL	SN74AS136N	SN74AS194D
SN74ALVC16828DGG	SN74AS137D	SN74AS194N
SN74ALVC16828DL	SN74AS137N	SN74AS195D
SN74ALVC16841DGG	SN74AS138D	SN74AS195N
SN74ALVC16841DL	SN74AS138N	SN74AS20D
SN74ALVC16843DGG	SN74AS151D	SN74AS20N
SN74ALVC16843DL	SN74AS151N	SN74AS21D
SN74ALVC16952DGG	SN74AS153D	SN74AS21N
SN74ALVC16952DL	SN74AS153N	SN74AS230DW
SN74AS00D	SN74AS157D	SN74AS230N
SN74AS00N	SN74AS157N	SN74AS240DW
SN74AS02D	SN74AS158D	SN74AS240N
SN74AS02N	SN74AS158N	SN74AS241D
SN74AS04D	SN74AS160D	SN74AS241N
SN74AS04N	SN74AS160N	SN74AS242D
SN74AS08D	SN74AS161D	SN74AS242N
SN74AS08N	SN74AS161N	SN74AS243AD
SN74AS1000AD	SN74AS162D	SN74AS243AN
SN74AS1000AN	SN74AS162N	SN74AS244DW

Appendix A: Digital Integrated Circuits included in P-CAD Signal Integrity

SN74AS1004AD	SN74AS163D	SN74AS244N
SN74AS1004AN	SN74AS163N	SN74AS245DW
SN74AS1008AD	SN74AS169AD	SN74AS245N
SN74AS1008AN	SN74AS169AN	SN74AS250ADW
SN74AS1032AD	SN74AS174D	SN74AS250ANT
SN74AS1032AN	SN74AS174N	SN74AS251D
SN74AS251N	SN74AS353AN	SN74AS644N
SN74AS253D	SN74AS373DW	SN74AS645DW
SN74AS253N	SN74AS373N	SN74AS645N
SN74AS257D	SN74AS374DW	SN74AS646DW
SN74AS257N	SN74AS374N	SN74AS646NT
SN74AS258D	SN74AS4374BDW	SN74AS648DW
SN74AS258N	SN74AS4374BN	SN74AS648NT
SN74AS2623DW	SN74AS533DW	SN74AS651DW
SN74AS2623N	SN74AS533N	SN74AS651NT
SN74AS2640DW	SN74AS534DW	SN74AS652DW
SN74AS2640N	SN74AS534N	SN74AS652NT
SN74AS2645DW	SN74AS573ADW	SN74AS74D
SN74AS2645N	SN74AS573AN	SN74AS74N
SN74AS27D	SN74AS574DW	SN74AS756DW
SN74AS27N	SN74AS574N	SN74AS756N
SN74AS280D	SN74AS575DW	SN74AS757DW
SN74AS280N	SN74AS575NT	SN74AS757N
SN74AS286D	SN74AS576DW	SN74AS759D
SN74AS286N	SN74AS576N	SN74AS759N
SN74AS298D	SN74AS577DW	SN74AS760DW
SN74AS298N	SN74AS577NT	SN74AS760N
SN74AS299DW	SN74AS580DW	SN74AS762DW
SN74AS299N	SN74AS580N	SN74AS762N
SN74AS303D	SN74AS620DW	SN74AS763DW
SN74AS303N	SN74AS620N	SN74AS763N
SN74AS304D	SN74AS623DW	SN74AS804BDW
SN74AS304N	SN74AS623N	SN74AS804BN

Appendix A: Digital Integrated Circuits included in P-CAD Signal Integrity

CNIZAA COOFD	CNIZAA CC20A DVA/	CNIZ4A COOFDINA/
SN74AS305D	SN74AS638ADW	SN74AS805BDW
SN74AS305N	SN74AS638AN	SN74AS805BN
SN74AS30D	SN74AS639DW	SN74AS808BDW
SN74AS30N	SN74AS639N	SN74AS808BN
SN74AS323DW	SN74AS640DW	SN74AS810D
SN74AS323N	SN74AS640N	SN74AS810N
SN74AS32D	SN74AS641DW	SN74AS811D
SN74AS32N	SN74AS641N	SN74AS811N
SN74AS34D	SN74AS642DW	SN74AS821DW
SN74AS34N	SN74AS642N	SN74AS821NT
SN74AS352D	SN74AS643DW	SN74AS822DW
SN74AS352N	SN74AS643N	SN74AS822NT
SN74AS353AD	SN74AS644DW	SN74AS823DW
SN74AS823NT	SN74AS885NT	SN74BCT29841NT
SN74AS824DW	SN74BCT2240DB	SN74BCT29843DW
SN74AS824NT	SN74BCT2240DW	SN74BCT29843NT
SN74AS825DW	SN74BCT2240N	SN74BCT29854DW
SN74AS825NT	SN74BCT2241DB	SN74BCT29854NT
SN74AS826DW	SN74BCT2241DW	SN74BCT29863ADW
SN74AS826NT	SN74BCT2241N	SN74BCT29863ANT
SN74AS832BDW	SN74BCT2244DW	SN74BCT373DB
SN74AS832BN	SN74BCT2244N	SN74BCT373DW
SN74AS856DW	SN74BCT240DB	SN74BCT373N
SN74AS856NT	SN74BCT240DW	SN74BCT374DB
SN74AS857ADW	SN74BCT240N	SN74BCT374DW
SN74AS857ANT	SN74BCT241DB	SN74BCT374N
SN74AS867DW	SN74BCT241DW	SN74BCT540ADW
SN74AS867NT	SN74BCT241N	SN74BCT540AN
SN74AS869DW	SN74BCT244DB	SN74BCT541ADW
SN74AS869NT	SN74BCT244DW	SN74BCT541AN
SN74AS86AD	SN74BCT244N	SN74BCT543DW
SN74AS86AN	SN74BCT245DB	SN74BCT543NT
SN74AS870DW	SN74BCT245DW	SN74BCT620ADW

Appendix A: Digital Integrated Circuits included in P-CAD Signal Integrity

SN74AS870NT	SN74BCT245N	SN74BCT620AN
SN74AS873ADW	SN74BCT25244DW	SN74BCT623DW
SN74AS873ANT	SN74BCT25244NT	SN74BCT623N
SN74AS874DW	SN74BCT25245DW	SN74BCT640DW
SN74AS874NT	SN74BCT25245NT	SN74BCT640N
SN74AS876DW	SN74BCT2827CDW	SN74BCT646DW
SN74AS876NT	SN74BCT2827CNT	SN74BCT646NT
SN74AS877DW	SN74BCT2828BDW	SN74BCT756DW
SN74AS877NT	SN74BCT2828BNT	SN74BCT756N
SN74AS878DW	SN74BCT29821DW	SN74BCT757DW
SN74AS878NT	SN74BCT29821NT	SN74BCT757N
SN74AS879DW	SN74BCT29823DW	SN74BCT760DW
SN74AS879NT	SN74BCT29823NT	SN74BCT760N
SN74AS880DW	SN74BCT29827BDW	SN74BCT8244DW
SN74AS880NT	SN74BCT29827BNT	SN74BCT8244NT
SN74AS881ADW	SN74BCT29828BDW	SN74F00D
SN74AS881ANT	SN74BCT29828BNT	SN74F00N
SN74AS882ADW	SN74BCT29834DW	SN74F02D
SN74AS882ANT	SN74BCT29834NT	SN74F02N
SN74AS885DW	SN74BCT29841DW	SN74F04D
SN74F04N	SN74F166N	SN74F27D
SN74F08D	SN74F168D	SN74F27N
SN74F08N	SN74F168N	SN74F280BD
SN74F09D	SN74F169D	SN74F280BN
SN74F09N	SN74F169N	SN74F283D
SN74F109D	SN74F174D	SN74F283N
SN74F109N	SN74F174N	SN74F286D
SN74F10D	SN74F175D	SN74F286N
SN74F10N	SN74F175N	SN74F299DW
SN74F112D	SN74F20D	SN74F299N
SN74F112N	SN74F20N	SN74F30D
SN74F113D	SN74F21D	SN74F30N
SN74F113N	SN74F21N	SN74F323DW
·		

Appendix A: Digital Integrated Circuits included in P-CAD Signal Integrity

SN74F114D	SN74F240DB	SN74F323N
SN74F114N	SN74F240DW	SN74F32D
SN74F11D	SN74F240N	SN74F32N
SN74F11N	SN74F241DW	SN74F350D
SN74F125D	SN74F241N	SN74F350N
SN74F125N	SN74F242D	SN74F352D
SN74F126D	SN74F242N	SN74F352N
SN74F126N	SN74F243D	SN74F353D
SN74F138D	SN74F243N	SN74F353N
SN74F138N	SN74F244DB	SN74F36D
SN74F151AD	SN74F244DW	SN74F36N
SN74F151AN	SN74F244N	SN74F373DB
SN74F153D	SN74F245DB	SN74F373DW
SN74F153N	SN74F245DW	SN74F373N
SN74F157AD	SN74F245N	SN74F374DB
SN74F157AN	SN74F251D	SN74F374DW
SN74F158AD	SN74F251N	SN74F374N
SN74F158AN	SN74F253D	SN74F377D
SN74F160AD	SN74F253N	SN74F377N
SN74F160AN	SN74F257D	SN74F378D
SN74F161AD	SN74F257N	SN74F378N
SN74F161AN	SN74F258D	SN74F379D
SN74F162AD	SN74F258N	SN74F379N
SN74F162AN	SN74F260D	SN74F37D
SN74F163AD	SN74F260N	SN74F37N
SN74F163AN	SN74F273DW	SN74F381DW
SN74F166D	SN74F273N	SN74F381N
SN74F382DW	SN74F574N	SN74HC05N
SN74F382N	SN74F620DW	SN74HC08D
SN74F38D	SN74F620N	SN74HC08DB
SN74F38N	SN74F621DW	SN74HC08N
SN74F40D	SN74F621N	SN74HC109D
SN74F40N	SN74F622DW	SN74HC109DB

Appendix A: Digital Integrated Circuits included in P-CAD Signal Integrity

SN74F518DW	SN74F622N	SN74HC109N
SN74F518N	SN74F623DW	SN74HC10D
SN74F519DW	SN74F623N	SN74HC10DB
SN74F519N	SN74F64D	SN74HC10N
SN74F51D	SN74F64N	SN74HC112D
SN74F51N	SN74F657DW	SN74HC112DB
SN74F520DW	SN74F657N	SN74HC112N
SN74F520N	SN74F74D	SN74HC11D
SN74F521DW	SN74F74N	SN74HC11DB
SN74F521N	SN74F86D	SN74HC11N
SN74F533DW	SN74F86N	SN74HC125D
SN74F533N	SN74FB1650PCA	SN74HC125DB
SN74F534DW	SN74FB1651PCA	SN74HC125N
SN74F534N	SN74FB2031RC	SN74HC126D
SN74F540DW	SN74FB2032RC	SN74HC126DB
SN74F540N	SN74FB2033ARC	SN74HC126N
SN74F541DW	SN74FB2040RC	SN74HC132D
SN74F541N	SN74FB2041RC	SN74HC132DB
SN74F543DB	SN74GTL16612DGG	SN74HC132N
SN74F543DW	SN74GTL16612DL	SN74HC138D
SN74F543N	SN74HC00D	SN74HC138DB
SN74F544DW	SN74HC00DB	SN74HC138N
SN74F544N	SN74HC00N	SN74HC139D
SN74F563DW	SN74HC02D	SN74HC139DB
SN74F563N	SN74HC02DB	SN74HC139N
SN74F564DW	SN74HC02N	SN74HC148N
SN74F564N	SN74HC03D	SN74HC14D
SN74F568DW	SN74HC03DB	SN74HC14DB
SN74F568N	SN74HC03N	SN74HC14N
SN74F569DW	SN74HC04D	SN74HC151D
SN74F569N	SN74HC04DB	SN74HC151DB
SN74F573DW	SN74HC04N	SN74HC151N
SN74F573N	SN74HC05D	SN74HC153D
•		

Appendix A: Digital Integrated Circuits included in P-CAD Signal Integrity

SN74F574DW	SN74HC05DB	SN74HC153DB
SN74HC153N	SN74HC240N	SN74HC367D
SN74HC157D	SN74HC241DB	SN74HC367DB
SN74HC157DB	SN74HC241DW	SN74HC367N
SN74HC157N	SN74HC241N	SN74HC368D
SN74HC158D	SN74HC244DB	SN74HC368DB
SN74HC158DB	SN74HC244DW	SN74HC368N
SN74HC158N	SN74HC244N	SN74HC373DB
SN74HC161D	SN74HC245DB	SN74HC373DW
SN74HC161DB	SN74HC245DW	SN74HC373N
SN74HC161N	SN74HC245N	SN74HC374DB
SN74HC163D	SN74HC251D	SN74HC374DW
SN74HC163DB	SN74HC251DB	SN74HC374N
SN74HC163N	SN74HC251N	SN74HC377DB
SN74HC164D	SN74HC253D	SN74HC377DW
SN74HC164DB	SN74HC253DB	SN74HC377N
SN74HC164N	SN74HC253N	SN74HC393D
SN74HC165D	SN74HC257D	SN74HC393DB
SN74HC165DB	SN74HC257DB	SN74HC393N
SN74HC165N	SN74HC257N	SN74HC4020D
SN74HC166D	SN74HC258D	SN74HC4020DB
SN74HC166DB	SN74HC258DB	SN74HC4020N
SN74HC166N	SN74HC258N	SN74HC4040D
SN74HC174D	SN74HC259D	SN74HC4040DB
SN74HC174DB	SN74HC259DB	SN74HC4040N
SN74HC174N	SN74HC259N	SN74HC4060D
SN74HC175D	SN74HC266D	SN74HC4060DB
SN74HC175DB	SN74HC266DB	SN74HC4060N
SN74HC175N	SN74HC266N	SN74HC42N
SN74HC191N	SN74HC273DB	SN74HC534DW
SN74HC193D	SN74HC273DW	SN74HC534N
SN74HC193DB	SN74HC273N	SN74HC540DB
SN74HC193N	SN74HC27D	SN74HC540DW
-		

Appendix A: Digital Integrated Circuits included in P-CAD Signal Integrity

SN74HC20D         SN74HC27DB         SN74HC541DB           SN74HC20DB         SN74HC27N         SN74HC541DB           SN74HC20N         SN74HC32D         SN74HC541DW           SN74HC21D         SN74HC32DB         SN74HC541DW           SN74HC21DB         SN74HC32DB         SN74HC563DW           SN74HC21DB         SN74HC36D         SN74HC563DW           SN74HC24DB         SN74HC365D         SN74HC563N           SN74HC240DW         SN74HC365DB         SN74HC573ADB           SN74HC240DW         SN74HC365N         SN74HC573ADW           SN74HC573AN         SN74HC7032D         SN74HC1245N           SN74HC573DB         SN74HC7032DB         SN74HC1257D           SN74HC573DW         SN74HC7032N         SN74HC1257N           SN74HC573DW         SN74HC74DB         SN74HC1273DW           SN74HC574DB         SN74HC74DB         SN74HC1273DW           SN74HC574DB         SN74HC74DB         SN74HC1732DW           SN74HC574DW         SN74HC66D         SN74HC132D           SN74HC594DW         SN74HC86DB         SN74HC132D           SN74HC599DN         SN74HC86DB         SN74HC132D           SN74HC594DW         SN74HC100D         SN74HC1373DW           SN74HC595DB         SN74HC			
SN74HC20N         SN74HC32D         SN74HC541DW           SN74HC21D         SN74HC32DB         SN74HC541N           SN74HC21DB         SN74HC32N         SN74HC563DW           SN74HC21N         SN74HC365D         SN74HC563N           SN74HC240DB         SN74HC365DB         SN74HC573ADB           SN74HC240DW         SN74HC365N         SN74HC573ADW           SN74HC573AN         SN74HC7032D         SN74HC273ADW           SN74HC573DB         SN74HC7032DB         SN74HC7257D           SN74HC573DW         SN74HC7032N         SN74HC7257N           SN74HC573DW         SN74HC74D         SN74HC7273DB           SN74HC573DW         SN74HC74D         SN74HC7273DW           SN74HC574DB         SN74HC74DB         SN74HC7273DW           SN74HC574DW         SN74HC74N         SN74HC732D           SN74HC594DW         SN74HC86D         SN74HC732D           SN74HC599DD         SN74HC86DB         SN74HC732DB           SN74HC594DW         SN74HC700D         SN74HC7373DB           SN74HC594DW         SN74HC700DB         SN74HC7373DW           SN74HC595DB         SN74HC700DB         SN74HC7373DW           SN74HC709DB         SN74HC737AD         SN74HC737AD           SN74HC695N	SN74HC20D	SN74HC27DB	SN74HC540N
SN74HC21D         SN74HC32DB         SN74HC541N           SN74HC21DB         SN74HC32N         SN74HC563DW           SN74HC21N         SN74HC365D         SN74HC563N           SN74HC240DB         SN74HC365DB         SN74HC573ADB           SN74HC240DW         SN74HC365N         SN74HC573ADW           SN74HC573AN         SN74HC7032D         SN74HC245N           SN74HC573DB         SN74HC7032DB         SN74HC1257D           SN74HC573DW         SN74HC7032N         SN74HC1257N           SN74HC573DW         SN74HC7032N         SN74HC1273DB           SN74HC573N         SN74HC74D         SN74HC1273DB           SN74HC574DB         SN74HC174DB         SN74HC1273DW           SN74HC574DW         SN74HC74N         SN74HC1273N           SN74HC594DW         SN74HC86D         SN74HC132D           SN74HC590D         SN74HC86DB         SN74HC132D           SN74HC594DW         SN74HC100D         SN74HC132N           SN74HC594DW         SN74HC100D         SN74HC1373DB           SN74HC595DB         SN74HC100D         SN74HC1373DW           SN74HC595DW         SN74HC102D         SN74HC1374DW           SN74HC23DW         SN74HC102D         SN74HC1374DW           SN74HC640DB         S	SN74HC20DB	SN74HC27N	SN74HC541DB
SN74HC21DB         SN74HC32N         SN74HC563DW           SN74HC21N         SN74HC365D         SN74HC563N           SN74HC240DB         SN74HC365DB         SN74HC573ADB           SN74HC240DW         SN74HC365N         SN74HC573ADW           SN74HC573AN         SN74HC7032D         SN74HC725TD           SN74HC573DB         SN74HC7032DB         SN74HC7257D           SN74HC573DW         SN74HC7032N         SN74HC725TN           SN74HC573N         SN74HC74D         SN74HC7273DB           SN74HC574DB         SN74HC74DB         SN74HC7273DW           SN74HC574DB         SN74HC74N         SN74HC7273DW           SN74HC574DW         SN74HC74N         SN74HC732D           SN74HC574N         SN74HC86D         SN74HC732D           SN74HC590D         SN74HC86DB         SN74HC732D           SN74HC590N         SN74HC86N         SN74HC732D           SN74HC594DW         SN74HC700D         SN74HC737DB           SN74HC594N         SN74HC700D         SN74HC737DW           SN74HC595DB         SN74HC700D         SN74HC737AD           SN74HC702D         SN74HC737AD           SN74HC703D         SN74HC737AD           SN74HC623DW         SN74HC702D         SN74HC737AD	SN74HC20N	SN74HC32D	SN74HC541DW
SN74HC21N         SN74HC365D         SN74HC563N           SN74HC240DB         SN74HC365DB         SN74HC573ADB           SN74HC240DW         SN74HC365N         SN74HC573ADW           SN74HC573AN         SN74HC7032D         SN74HC7245N           SN74HC573DB         SN74HC7032DB         SN74HC725TD           SN74HC573DW         SN74HC7032N         SN74HC725TN           SN74HC573DW         SN74HC74D         SN74HC727DB           SN74HC574DB         SN74HC74DB         SN74HC7273DW           SN74HC574DW         SN74HC74DB         SN74HC7273DW           SN74HC574DW         SN74HC74N         SN74HC7273N           SN74HC594DW         SN74HC86DB         SN74HC732D           SN74HC590D         SN74HC86DB         SN74HC732DB           SN74HC594DW         SN74HC700D         SN74HC732DB           SN74HC594DW         SN74HC700DB         SN74HC737DB           SN74HC595DB         SN74HC700DB         SN74HC737DW           SN74HC595DW         SN74HC702D         SN74HC737ADB           SN74HC702D         SN74HC737ADB           SN74HC702D         SN74HC737ADW           SN74HC623N         SN74HC702DB         SN74HC737AD           SN74HC704DB         SN74HC737AD           SN	SN74HC21D	SN74HC32DB	SN74HC541N
SN74HC240DB         SN74HC365DB         SN74HC573ADB           SN74HC240DW         SN74HC365N         SN74HC573ADW           SN74HC573AN         SN74HC7032D         SN74HC7245N           SN74HC573DB         SN74HC7032DB         SN74HC7257D           SN74HC573DW         SN74HC7032N         SN74HC725TN           SN74HC573DW         SN74HC74D         SN74HC727DB           SN74HC574DB         SN74HC74DB         SN74HC7273DW           SN74HC574DW         SN74HC74DB         SN74HC7273DW           SN74HC574DW         SN74HC74N         SN74HC7273N           SN74HC594DW         SN74HC86D         SN74HC732D           SN74HC590D         SN74HC86DB         SN74HC732DB           SN74HC594DW         SN74HC86N         SN74HC732DB           SN74HC594DW         SN74HC700D         SN74HC737DB           SN74HC595H         SN74HC700DB         SN74HC737DW           SN74HC595DB         SN74HC702D         SN74HC737ADB           SN74HC702D         SN74HC737ADB           SN74HC695N         SN74HC702D         SN74HC737ADW           SN74HC603DW         SN74HC702DB         SN74HC737AD           SN74HC603DW         SN74HC704D         SN74HC737DB           SN74HC640DB         SN74HC704DB	SN74HC21DB	SN74HC32N	SN74HC563DW
SN74HC240DW         SN74HC365N         SN74HC573ADW           SN74HC573AN         SN74HC7032D         SN74HCT245N           SN74HC573DB         SN74HC7032DB         SN74HCT257D           SN74HC573DW         SN74HC7032N         SN74HCT257N           SN74HC573DW         SN74HC74D         SN74HCT273DB           SN74HC574DB         SN74HC74DB         SN74HCT273DW           SN74HC574DW         SN74HC74N         SN74HCT273N           SN74HC574DW         SN74HC86D         SN74HCT32D           SN74HC594DW         SN74HC86DB         SN74HCT32DB           SN74HC590D         SN74HC86N         SN74HC732DB           SN74HC594DW         SN74HC700D         SN74HC737DB           SN74HC594DW         SN74HC700DB         SN74HC7373DW           SN74HC595DB         SN74HC700D         SN74HC7373DW           SN74HC595DW         SN74HC702D         SN74HC7374DB           SN74HC595DW         SN74HC702D         SN74HC7374DW           SN74HC623DW         SN74HC702D         SN74HC7374DW           SN74HC623DW         SN74HC704D         SN74HC737DB           SN74HC640DB         SN74HC737DW         SN74HC640DB         SN74HC737DN           SN74HC640DW         SN74HC708D         SN74HC7540DW         SN74HC754	SN74HC21N	SN74HC365D	SN74HC563N
SN74HC573AN         SN74HC7032D         SN74HC7245N           SN74HC573DB         SN74HC7032DB         SN74HC7257D           SN74HC573DW         SN74HC7032N         SN74HC7257N           SN74HC573N         SN74HC74D         SN74HC723DB           SN74HC574DB         SN74HC74DB         SN74HC723DW           SN74HC574DW         SN74HC74N         SN74HC7273N           SN74HC574DW         SN74HC86D         SN74HC132D           SN74HC594DW         SN74HC86DB         SN74HC132DB           SN74HC590D         SN74HC86N         SN74HC132D           SN74HC594DW         SN74HC10DD         SN74HC132D           SN74HC594DW         SN74HC10DD         SN74HC1373DB           SN74HC594DW         SN74HC100D         SN74HC1373DW           SN74HC595DB         SN74HC100N         SN74HC1373N           SN74HC595DW         SN74HC102D         SN74HC1374DB           SN74HC595N         SN74HC102D         SN74HC1374DW           SN74HC623DW         SN74HC102D         SN74HC1374DW           SN74HC623N         SN74HC104D         SN74HC1377DB           SN74HC640DB         SN74HC104D         SN74HC1377DW           SN74HC640DW         SN74HC104D         SN74HC1540DW           SN74HC645DW <t< td=""><td>SN74HC240DB</td><td>SN74HC365DB</td><td>SN74HC573ADB</td></t<>	SN74HC240DB	SN74HC365DB	SN74HC573ADB
SN74HC573DB         SN74HC7032DB         SN74HCT257D           SN74HC573DW         SN74HC7032N         SN74HCT257N           SN74HC573N         SN74HC74D         SN74HCT273DB           SN74HC574DB         SN74HC74DB         SN74HCT273DW           SN74HC574DW         SN74HC74N         SN74HCT273N           SN74HC574N         SN74HC86D         SN74HCT32D           SN74HC590D         SN74HC86DB         SN74HCT32DB           SN74HC590N         SN74HC86N         SN74HCT32D           SN74HC594DW         SN74HC100D         SN74HC132N           SN74HC594DW         SN74HC100DB         SN74HC1373DW           SN74HC595DB         SN74HC100DB         SN74HC1373DW           SN74HC595DB         SN74HC102D         SN74HC1374DB           SN74HC595DW         SN74HC102D         SN74HC1374DB           SN74HC595N         SN74HC102DB         SN74HC1374DW           SN74HC623DW         SN74HC102D         SN74HC1374N           SN74HC623N         SN74HC104D         SN74HC1377DB           SN74HC640DB         SN74HC104D         SN74HC1377N           SN74HC640N         SN74HC108D         SN74HC1540DB           SN74HC645DB         SN74HC125D         SN74HC1541DB           SN74HC645DW         <	SN74HC240DW	SN74HC365N	SN74HC573ADW
SN74HC573DW         SN74HC7032N         SN74HCT257N           SN74HC573N         SN74HC74D         SN74HCT273DB           SN74HC574DB         SN74HC74DB         SN74HCT273DW           SN74HC574DW         SN74HC74N         SN74HCT273N           SN74HC574N         SN74HC86D         SN74HCT32D           SN74HC590D         SN74HC86DB         SN74HCT32DB           SN74HC590N         SN74HC86N         SN74HCT32N           SN74HC594DW         SN74HC700D         SN74HCT37DB           SN74HC594DW         SN74HCT00DB         SN74HCT373DW           SN74HC595DB         SN74HCT00D         SN74HCT373DW           SN74HC595DW         SN74HCT02D         SN74HCT374DB           SN74HC595DW         SN74HCT02D         SN74HCT374DW           SN74HC623DW         SN74HCT02D         SN74HCT374DW           SN74HC623DW         SN74HCT02D         SN74HCT377DB           SN74HC640DB         SN74HCT04D         SN74HCT377DW           SN74HC640DW         SN74HCT04D         SN74HCT377N           SN74HC640DW         SN74HCT08D         SN74HCT540DB           SN74HC645DW         SN74HCT08D         SN74HCT540DW           SN74HC645DW         SN74HCT125D         SN74HCT541DB           SN74HC646DW	SN74HC573AN	SN74HC7032D	SN74HCT245N
SN74HC573N         SN74HC74D         SN74HC1273DB           SN74HC574DB         SN74HC74DB         SN74HC1273DW           SN74HC574DW         SN74HC74N         SN74HC1273N           SN74HC574N         SN74HC86D         SN74HC132D           SN74HC590D         SN74HC86DB         SN74HC132DB           SN74HC590N         SN74HC86N         SN74HC132N           SN74HC594DW         SN74HC100D         SN74HC1373DB           SN74HC594DW         SN74HC100DB         SN74HC1373DW           SN74HC595DB         SN74HC100N         SN74HC1373N           SN74HC595DW         SN74HC102D         SN74HC1374DB           SN74HC595N         SN74HC102DB         SN74HC1374DW           SN74HC623DW         SN74HC102N         SN74HC1374N           SN74HC623N         SN74HC104D         SN74HC1377DB           SN74HC640DB         SN74HC104DB         SN74HC1377DW           SN74HC640DW         SN74HC104D         SN74HC1377N           SN74HC640N         SN74HC108D         SN74HC1540DB           SN74HC104DB         SN74HC1540DW           SN74HC645DW         SN74HC108D         SN74HC1540DW           SN74HC645DW         SN74HC125D         SN74HC1541DW           SN74HC646NT         SN74HC1125N	SN74HC573DB	SN74HC7032DB	SN74HCT257D
SN74HC574DB         SN74HC74DB         SN74HCT273DW           SN74HC574DW         SN74HC74N         SN74HCT273N           SN74HC574N         SN74HC86D         SN74HCT32D           SN74HC590D         SN74HC86DB         SN74HCT32DB           SN74HC590N         SN74HC86N         SN74HCT32N           SN74HC594DW         SN74HC700D         SN74HCT373DB           SN74HC594DW         SN74HCT00DB         SN74HCT373DW           SN74HC595DB         SN74HCT00N         SN74HCT373N           SN74HC595DW         SN74HCT02D         SN74HCT374DB           SN74HC595N         SN74HCT02DB         SN74HCT374DW           SN74HC623DW         SN74HCT02N         SN74HCT374N           SN74HC623N         SN74HCT04D         SN74HCT377DB           SN74HC640DB         SN74HCT04DB         SN74HCT377N           SN74HC640DW         SN74HCT04D         SN74HCT377N           SN74HC640N         SN74HCT08D         SN74HCT540DW           SN74HC645DW         SN74HCT08N         SN74HCT541DW           SN74HC645N         SN74HCT125N         SN74HCT541DW           SN74HC646NT         SN74HCT138D         SN74HCT541N	SN74HC573DW	SN74HC7032N	SN74HCT257N
SN74HC574DW         SN74HC74N         SN74HC1273N           SN74HC574N         SN74HC86D         SN74HC132D           SN74HC590D         SN74HC86DB         SN74HC132DB           SN74HC590N         SN74HC86N         SN74HC132N           SN74HC594DW         SN74HC100D         SN74HC1373DB           SN74HC594DW         SN74HC100DB         SN74HC1373DW           SN74HC595DB         SN74HC100N         SN74HC1373DW           SN74HC595DW         SN74HC102D         SN74HC1374DB           SN74HC595N         SN74HC102DB         SN74HC1374DW           SN74HC623DW         SN74HC102N         SN74HC1374N           SN74HC623N         SN74HC104D         SN74HC1377DB           SN74HC640DB         SN74HC104DB         SN74HC1377DW           SN74HC640DW         SN74HC104N         SN74HC1377N           SN74HC640N         SN74HC108D         SN74HC1540DB           SN74HC645DB         SN74HC108D         SN74HC1540DW           SN74HC645DW         SN74HC125D         SN74HC1541DB           SN74HC646DW         SN74HC1125N         SN74HC1541DW           SN74HC646NT         SN74HC1138D         SN74HC1541N	SN74HC573N	SN74HC74D	SN74HCT273DB
SN74HC574N         SN74HC86D         SN74HCT32D           SN74HC590D         SN74HC86DB         SN74HCT32DB           SN74HC590N         SN74HC86N         SN74HCT32N           SN74HC594DW         SN74HCT00D         SN74HCT373DB           SN74HC594N         SN74HCT00DB         SN74HCT373DW           SN74HC595NB         SN74HCT00N         SN74HCT373N           SN74HC595DW         SN74HCT02D         SN74HCT374DB           SN74HC595N         SN74HCT02DB         SN74HCT374DW           SN74HC623DW         SN74HCT02N         SN74HCT374N           SN74HC623N         SN74HCT04D         SN74HCT377DB           SN74HC640DB         SN74HCT04DB         SN74HCT377N           SN74HC640DW         SN74HCT04D         SN74HCT377N           SN74HC640N         SN74HCT08D         SN74HCT540DB           SN74HC645DB         SN74HCT08DB         SN74HCT540DW           SN74HC645N         SN74HCT125D         SN74HCT541DB           SN74HC646DW         SN74HCT125N         SN74HCT541DW           SN74HC646NT         SN74HCT138D         SN74HCT541N	SN74HC574DB	SN74HC74DB	SN74HCT273DW
SN74HC590D         SN74HC86DB         SN74HCT32DB           SN74HC590N         SN74HC86N         SN74HCT32N           SN74HC594DW         SN74HCT00D         SN74HCT373DB           SN74HC594N         SN74HCT00DB         SN74HCT373DW           SN74HC595DB         SN74HCT00N         SN74HCT373N           SN74HC595DW         SN74HCT02D         SN74HCT374DB           SN74HC595N         SN74HCT02DB         SN74HCT374DW           SN74HC623DW         SN74HCT02D         SN74HCT374DW           SN74HC623N         SN74HCT04D         SN74HCT377DB           SN74HC640DB         SN74HCT04DB         SN74HCT377DW           SN74HC640DW         SN74HCT04D         SN74HCT377N           SN74HC640N         SN74HCT08D         SN74HCT540DB           SN74HC645DB         SN74HCT08DB         SN74HCT540DW           SN74HC645N         SN74HCT125D         SN74HCT541DB           SN74HC645N         SN74HCT125D         SN74HCT541DW           SN74HC646NT         SN74HCT138D         SN74HCT541N	SN74HC574DW	SN74HC74N	SN74HCT273N
SN74HC590N         SN74HC86N         SN74HCT32N           SN74HC594DW         SN74HCT00D         SN74HCT373DB           SN74HC594N         SN74HCT00DB         SN74HCT373DW           SN74HC595DB         SN74HCT00N         SN74HCT373N           SN74HC595DW         SN74HCT02D         SN74HCT374DB           SN74HC595N         SN74HCT02DB         SN74HCT374DW           SN74HC623DW         SN74HCT02N         SN74HCT374N           SN74HC623N         SN74HCT04D         SN74HCT377DB           SN74HC640DB         SN74HCT04DB         SN74HCT377DW           SN74HC640DW         SN74HCT04N         SN74HCT377N           SN74HC640N         SN74HCT08D         SN74HCT540DB           SN74HC645DB         SN74HCT08DB         SN74HCT540DW           SN74HC645N         SN74HCT125D         SN74HCT541DB           SN74HC645N         SN74HCT125N         SN74HCT541DW           SN74HC646NT         SN74HCT138D         SN74HCT541N	SN74HC574N	SN74HC86D	SN74HCT32D
SN74HC594DW         SN74HCT00D         SN74HCT373DB           SN74HC594N         SN74HCT00DB         SN74HCT373DW           SN74HC595DB         SN74HCT00N         SN74HCT373N           SN74HC595DW         SN74HCT02D         SN74HCT374DB           SN74HC595N         SN74HCT02DB         SN74HCT374DW           SN74HC623DW         SN74HCT02N         SN74HCT374N           SN74HC623N         SN74HCT04D         SN74HCT377DB           SN74HC640DB         SN74HCT04DB         SN74HCT377DW           SN74HC640DW         SN74HCT04N         SN74HCT377N           SN74HC640N         SN74HCT08D         SN74HCT540DB           SN74HC645DB         SN74HCT08DB         SN74HCT540DW           SN74HC645DW         SN74HCT08N         SN74HCT541DB           SN74HC645N         SN74HCT125D         SN74HCT541DB           SN74HC646DW         SN74HCT125N         SN74HCT541DW           SN74HC646NT         SN74HCT138D         SN74HCT541N	SN74HC590D	SN74HC86DB	SN74HCT32DB
SN74HC594N         SN74HCT00DB         SN74HCT373DW           SN74HC595DB         SN74HCT00N         SN74HCT373N           SN74HC595DW         SN74HCT02D         SN74HCT374DB           SN74HC595N         SN74HCT02DB         SN74HCT374DW           SN74HC623DW         SN74HCT02N         SN74HCT374N           SN74HC623N         SN74HCT04D         SN74HCT377DB           SN74HC640DB         SN74HCT04DB         SN74HCT377DW           SN74HC640DW         SN74HCT04N         SN74HCT377N           SN74HC640N         SN74HCT08D         SN74HCT540DB           SN74HC645DB         SN74HCT08DB         SN74HCT540DW           SN74HC645DW         SN74HCT08N         SN74HCT540N           SN74HC645N         SN74HCT125D         SN74HCT541DB           SN74HC666DW         SN74HCT125N         SN74HCT541DW           SN74HC646NT         SN74HCT138D         SN74HCT541N	SN74HC590N	SN74HC86N	SN74HCT32N
SN74HC595DB         SN74HCT00N         SN74HCT373N           SN74HC595DW         SN74HCT02D         SN74HCT374DB           SN74HC595N         SN74HCT02DB         SN74HCT374DW           SN74HC623DW         SN74HCT02N         SN74HCT374N           SN74HC623N         SN74HCT04D         SN74HCT377DB           SN74HC640DB         SN74HCT04DB         SN74HCT377DW           SN74HC640DW         SN74HCT04N         SN74HCT377N           SN74HC640N         SN74HCT08D         SN74HCT540DB           SN74HC645DB         SN74HCT540DW           SN74HC645DW         SN74HCT08N         SN74HCT540N           SN74HC645N         SN74HCT125D         SN74HCT541DB           SN74HC646DW         SN74HCT125N         SN74HCT541DW           SN74HC646NT         SN74HCT138D         SN74HCT541N	SN74HC594DW	SN74HCT00D	SN74HCT373DB
SN74HC595DW         SN74HCT02D         SN74HCT374DB           SN74HC595N         SN74HCT02DB         SN74HCT374DW           SN74HC623DW         SN74HCT02N         SN74HCT374N           SN74HC623N         SN74HCT04D         SN74HCT377DB           SN74HC640DB         SN74HCT04DB         SN74HCT377DW           SN74HC640DW         SN74HCT04N         SN74HCT377N           SN74HC640N         SN74HCT08D         SN74HCT540DB           SN74HC645DB         SN74HCT08DB         SN74HCT540DW           SN74HC645DW         SN74HCT08N         SN74HCT540N           SN74HC645N         SN74HCT125D         SN74HCT541DB           SN74HC646DW         SN74HCT125N         SN74HCT541DW           SN74HC646NT         SN74HCT138D         SN74HCT541N	SN74HC594N	SN74HCT00DB	SN74HCT373DW
SN74HC595N         SN74HCT02DB         SN74HCT374DW           SN74HC623DW         SN74HCT02N         SN74HCT374N           SN74HC623N         SN74HCT04D         SN74HCT377DB           SN74HC640DB         SN74HCT04DB         SN74HCT377DW           SN74HC640DW         SN74HCT04N         SN74HCT377N           SN74HC640N         SN74HCT08D         SN74HCT540DB           SN74HC645DB         SN74HCT540DW         SN74HCT540DW           SN74HC645DW         SN74HCT08N         SN74HCT541DB           SN74HC645N         SN74HCT125D         SN74HCT541DB           SN74HC646DW         SN74HCT125N         SN74HCT541DW           SN74HC646NT         SN74HCT138D         SN74HCT541N	SN74HC595DB	SN74HCT00N	SN74HCT373N
SN74HC623DW         SN74HCT02N         SN74HCT374N           SN74HC623N         SN74HCT04D         SN74HCT377DB           SN74HC640DB         SN74HCT04DB         SN74HCT377DW           SN74HC640DW         SN74HCT04N         SN74HCT377N           SN74HC640N         SN74HCT08D         SN74HCT540DB           SN74HC645DB         SN74HCT540DW         SN74HCT540DW           SN74HC645DW         SN74HCT08N         SN74HCT540N           SN74HC645N         SN74HCT125D         SN74HCT541DB           SN74HC646DW         SN74HCT125N         SN74HCT541DW           SN74HC646NT         SN74HCT138D         SN74HCT541N	SN74HC595DW	SN74HCT02D	SN74HCT374DB
SN74HC623N         SN74HCT04D         SN74HCT377DB           SN74HC640DB         SN74HCT04DB         SN74HCT377DW           SN74HC640DW         SN74HCT04N         SN74HCT377N           SN74HC640N         SN74HCT08D         SN74HCT540DB           SN74HC645DB         SN74HCT540DW           SN74HC645DW         SN74HCT08N         SN74HCT540N           SN74HC645N         SN74HCT125D         SN74HCT541DB           SN74HC646DW         SN74HCT125N         SN74HCT541DW           SN74HC646NT         SN74HCT138D         SN74HCT541N	SN74HC595N	SN74HCT02DB	SN74HCT374DW
SN74HC640DB         SN74HCT04DB         SN74HCT377DW           SN74HC640DW         SN74HCT04N         SN74HCT377N           SN74HC640N         SN74HCT08D         SN74HCT540DB           SN74HC645DB         SN74HCT540DW         SN74HCT540DW           SN74HC645DW         SN74HCT08N         SN74HCT540N           SN74HC645N         SN74HCT125D         SN74HCT541DB           SN74HC646DW         SN74HCT125N         SN74HCT541DW           SN74HC646NT         SN74HCT138D         SN74HCT541N	SN74HC623DW	SN74HCT02N	SN74HCT374N
SN74HC640DW         SN74HCT04N         SN74HCT377N           SN74HC640N         SN74HCT08D         SN74HCT540DB           SN74HC645DB         SN74HCT540DW           SN74HC645DW         SN74HCT08N         SN74HCT540N           SN74HC645N         SN74HCT125D         SN74HCT541DB           SN74HC646DW         SN74HCT125N         SN74HCT541DW           SN74HC646NT         SN74HCT138D         SN74HCT541N	SN74HC623N	SN74HCT04D	SN74HCT377DB
SN74HC640N         SN74HCT08D         SN74HCT540DB           SN74HC645DB         SN74HCT540DW           SN74HC645DW         SN74HCT08N         SN74HCT540N           SN74HC645N         SN74HCT125D         SN74HCT541DB           SN74HC646DW         SN74HCT125N         SN74HCT541DW           SN74HC646NT         SN74HCT138D         SN74HCT541N	SN74HC640DB	SN74HCT04DB	SN74HCT377DW
SN74HC645DB         SN74HCT08DB         SN74HCT540DW           SN74HC645DW         SN74HCT08N         SN74HCT540N           SN74HC645N         SN74HCT125D         SN74HCT541DB           SN74HC646DW         SN74HCT125N         SN74HCT541DW           SN74HC646NT         SN74HCT138D         SN74HCT541N	SN74HC640DW	SN74HCT04N	SN74HCT377N
SN74HC645DW         SN74HCT08N         SN74HCT540N           SN74HC645N         SN74HCT125D         SN74HCT541DB           SN74HC646DW         SN74HCT125N         SN74HCT541DW           SN74HC646NT         SN74HCT138D         SN74HCT541N	SN74HC640N	SN74HCT08D	SN74HCT540DB
SN74HC645N         SN74HCT125D         SN74HCT541DB           SN74HC646DW         SN74HCT125N         SN74HCT541DW           SN74HC646NT         SN74HCT138D         SN74HCT541N	SN74HC645DB	SN74HCT08DB	SN74HCT540DW
SN74HC646DW         SN74HCT125N         SN74HCT541DW           SN74HC646NT         SN74HCT138D         SN74HCT541N	SN74HC645DW	SN74HCT08N	SN74HCT540N
SN74HC646NT SN74HCT138D SN74HCT541N	SN74HC645N	SN74HCT125D	SN74HCT541DB
	SN74HC646DW	SN74HCT125N	SN74HCT541DW
SN74HC652DW SN74HCT138DB SN74HCT573DB	SN74HC646NT	SN74HCT138D	SN74HCT541N
	SN74HC652DW	SN74HCT138DB	SN74HCT573DB

Appendix A: Digital Integrated Circuits included in P-CAD Signal Integrity

SN74HC652NT	SN74HCT138N	SN74HCT573DW
SN74HC682DW	SN74HCT139D	SN74HCT573N
SN74HC682N	SN74HCT139DB	SN74HCT574DB
SN74HC684DW	SN74HCT139N	SN74HCT574DW
SN74HC684N	SN74HCT157D	SN74HCT574N
SN74HC688DB	SN74HCT157DB	SN74HCT623DW
SN74HC688DW	SN74HCT157N	SN74HCT623N
SN74HC688N	SN74HCT240DB	SN74HCT640DB
SN74HC688PW	SN74HCT240DW	SN74HCT640DW
SN74HC7001D	SN74HCT240N	SN74HCT640N
SN74HC7001DB	SN74HCT244DB	SN74HCT645DB
SN74HC7001N	SN74HCT244DW	SN74HCT645DW
SN74HC7002D	SN74HCT244N	SN74HCT645N
SN74HC7002DB	SN74HCT245DB	SN74HCT646DW
SN74HC7002N	SN74HCT245DW	SN74HCT646NT
SN74HCT652DW	SN74LS107AD	SN74LS126AD
SN74HCT652NT	SN74LS107AFK	SN74LS126AFK
SN74HCT74D	SN74LS107AJ	SN74LS126AJ
SN74HCT74DB	SN74LS107AN	SN74LS126AN
SN74HCT74N	SN74LS109AD	SN74LS12D
SN74HCU04D	SN74LS109AFK	SN74LS12FK
SN74HCU04DB	SN74LS109AJ	SN74LS12J
SN74HCU04N	SN74LS109AN	SN74LS12N
SN74LS00D	SN74LS10D	SN74LS132D
SN74LS00FK	SN74LS10FK	SN74LS132FK
SN74LS00J	SN74LS10J	SN74LS132J
SN74LS00N	SN74LS10N	SN74LS132N
SN74LS01D	SN74LS112AD	SN74LS136D
SN74LS01FK	SN74LS112AFK	SN74LS136FK
SN74LS01J	SN74LS112AJ	SN74LS136J
SN74LS01N	SN74LS112AN	SN74LS136N
SN74LS02D	SN74LS113AD	SN74LS137D
SN74LS02FK	SN74LS113AFK	SN74LS137FK
-		

Appendix A: Digital Integrated Circuits included in P-CAD Signal Integrity

SN74LS02J	SN74LS113AJ	SN74LS137J
SN74LS02N	SN74LS113AN	SN74LS137N
SN74LS03D	SN74LS114AD	SN74LS138D
SN74LS03FK	SN74LS114AFK	SN74LS138FK
SN74LS03J	SN74LS114AJ	SN74LS138J
SN74LS03N	SN74LS114AN	SN74LS138N
SN74LS04D	SN74LS11D	SN74LS139AD
SN74LS04FK	SN74LS11FK	SN74LS139AFK
SN74LS04J	SN74LS11J	SN74LS139AJ
SN74LS04N	SN74LS11N	SN74LS139AN
SN74LS05D	SN74LS122D	SN74LS13D
SN74LS05FK	SN74LS122FK	SN74LS13FK
SN74LS05J	SN74LS122J	SN74LS13J
SN74LS05N	SN74LS122N	SN74LS13N
SN74LS08D	SN74LS123D	SN74LS14D
SN74LS08FK	SN74LS123FK	SN74LS14FK
SN74LS08J	SN74LS123J	SN74LS14J
SN74LS08N	SN74LS123N	SN74LS14N
SN74LS09D	SN74LS125AD	SN74LS151D
SN74LS09FK	SN74LS125AFK	SN74LS151FK
SN74LS09J	SN74LS125AJ	SN74LS151J
SN74LS09N	SN74LS125AN	SN74LS151N
SN74LS153D	SN74LS164D	SN74LS183D
SN74LS153FK	SN74LS164FK	SN74LS183FK
SN74LS153J	SN74LS164J	SN74LS183J
SN74LS153N	SN74LS164N	SN74LS183N
SN74LS155AD	SN74LS165AD	SN74LS18D
SN74LS155AFK	SN74LS165AFK	SN74LS18J
SN74LS155AJ	SN74LS165AJ	SN74LS18N
SN74LS155AN	SN74LS165AN	SN74LS190D
SN74LS156D	SN74LS166AD	SN74LS190FK
SN74LS156FK	SN74LS166AFK	SN74LS190J
SN74LS156J	SN74LS166AJ	SN74LS190N

Appendix A: Digital Integrated Circuits included in P-CAD Signal Integrity

SN74LS156N	SN74LS166AN	SN74LS191D
SN74LS157D	SN74LS169BD	SN74LS191FK
SN74LS157FK	SN74LS169BFK	SN74LS191J
SN74LS157J	SN74LS169BJ	SN74LS191N
SN74LS157N	SN74LS169BN	SN74LS192D
SN74LS158D	SN74LS170D	SN74LS192FK
SN74LS158FK	SN74LS170FK	SN74LS192J
SN74LS158J	SN74LS170J	SN74LS192N
SN74LS158N	SN74LS170N	SN74LS193D
SN74LS15D	SN74LS171D	SN74LS193FK
SN74LS15FK	SN74LS171FK	SN74LS193J
SN74LS15J	SN74LS171J	SN74LS193N
SN74LS15N	SN74LS171N	SN74LS194AD
SN74LS160AD	SN74LS173AD	SN74LS194AFK
SN74LS160AFK	SN74LS173AFK	SN74LS194AJ
SN74LS160AJ	SN74LS173AJ	SN74LS194AN
SN74LS160AN	SN74LS173AN	SN74LS195AD
SN74LS161AD	SN74LS174D	SN74LS195AFK
SN74LS161AFK	SN74LS174FK	SN74LS195AJ
SN74LS161AJ	SN74LS174J	SN74LS195AN
SN74LS161AN	SN74LS174N	SN74LS196D
SN74LS162AD	SN74LS175D	SN74LS196FK
SN74LS162AFK	SN74LS175FK	SN74LS196J
SN74LS162AJ	SN74LS175J	SN74LS196N
SN74LS162AN	SN74LS175N	SN74LS197D
SN74LS163AD	SN74LS181DW	SN74LS197FK
SN74LS163AFK	SN74LS181FK	SN74LS197J
SN74LS163AJ	SN74LS181J	SN74LS197N
SN74LS163AN	SN74LS181N	SN74LS19D
SN74LS19J	SN74LS245J	SN74LS261N
SN74LS19N	SN74LS245N	SN74LS266D
SN74LS20D	SN74LS247D	SN74LS266FK
SN74LS20FK	SN74LS247FK	SN74LS266J
-		

Appendix A: Digital Integrated Circuits included in P-CAD Signal Integrity

SN74LS20J         SN74LS247J         SN74LS26N           SN74LS20N         SN74LS247N         SN74LS26D           SN74LS21D         SN74LS248D         SN74LS26FK           SN74LS21FK         SN74LS248FK         SN74LS26B           SN74LS21J         SN74LS248B         SN74LS26N           SN74LS21D         SN74LS248N         SN74LS273DW           SN74LS221D         SN74LS249D         SN74LS273FK           SN74LS221FK         SN74LS249D         SN74LS273FK           SN74LS221FK         SN74LS249FK         SN74LS273J           SN74LS221J         SN74LS249FK         SN74LS273J           SN74LS221J         SN74LS249J         SN74LS273AD           SN74LS221D         SN74LS249N         SN74LS279AD           SN74LS22D         SN74LS24D         SN74LS279AFK           SN74LS22D         SN74LS24J         SN74LS279AJ           SN74LS22D         SN74LS24H         SN74LS279AJ           SN74LS22D         SN74LS24H         SN74LS27PAJ           SN74LS24D         SN74LS27PAJ         SN74LS27PAJ           SN74LS24D         SN74LS27PAJ         SN74LS27PAJ           SN74LS24D         SN74LS25TH         SN74LS27PAJ           SN74LS24DFK         SN74LS25TH         SN74LS28D			
SN74LS21D         SN74LS248D         SN74LS26FK           SN74LS21FK         SN74LS248FK         SN74LS26J           SN74LS21J         SN74LS248J         SN74LS26N           SN74LS21N         SN74LS248N         SN74LS27DW           SN74LS221D         SN74LS249D         SN74LS273FK           SN74LS221D         SN74LS249D         SN74LS273FK           SN74LS221FK         SN74LS249FK         SN74LS273J           SN74LS221J         SN74LS249FK         SN74LS273J           SN74LS221J         SN74LS249J         SN74LS273N           SN74LS221N         SN74LS249N         SN74LS279AD           SN74LS221D         SN74LS24D         SN74LS279AFK           SN74LS22D         SN74LS24D         SN74LS279AFK           SN74LS22I         SN74LS24I         SN74LS279AI           SN74LS22I         SN74LS24I         SN74LS279AI           SN74LS22I         SN74LS24IN         SN74LS27D           SN74LS240DW         SN74LS251D         SN74LS27D           SN74LS240FK         SN74LS251FK         SN74LS27D           SN74LS240FK         SN74LS251D         SN74LS280D           SN74LS240N         SN74LS253D         SN74LS280D           SN74LS240N         SN74LS253FK         SN74LS28	SN74LS20J	SN74LS247J	SN74LS266N
SN74LS21FK         SN74LS248J         SN74LS26N           SN74LS21J         SN74LS248J         SN74LS26N           SN74LS21N         SN74LS248N         SN74LS273DW           SN74LS221D         SN74LS249D         SN74LS273FK           SN74LS221FK         SN74LS249FK         SN74LS273J           SN74LS221FK         SN74LS249FK         SN74LS273J           SN74LS221J         SN74LS249J         SN74LS273N           SN74LS221N         SN74LS249N         SN74LS279AD           SN74LS22D         SN74LS24D         SN74LS279AD           SN74LS22D         SN74LS24J         SN74LS279AJ           SN74LS22D         SN74LS24J         SN74LS279AJ           SN74LS22D         SN74LS24J         SN74LS279AJ           SN74LS22J         SN74LS24N         SN74LS27D           SN74LS22D         SN74LS24N         SN74LS27D           SN74LS22D         SN74LS251D         SN74LS27D           SN74LS22D         SN74LS251B         SN74LS27D           SN74LS240W         SN74LS251FK         SN74LS27FK           SN74LS240FK         SN74LS251B         SN74LS280D           SN74LS240         SN74LS253D         SN74LS280F           SN74LS241D         SN74LS283D         SN74LS280D	SN74LS20N	SN74LS247N	SN74LS26D
SN74LS21J         SN74LS248J         SN74LS26N           SN74LS21N         SN74LS248N         SN74LS273DW           SN74LS221D         SN74LS249D         SN74LS273FK           SN74LS221FK         SN74LS249FK         SN74LS273J           SN74LS221J         SN74LS249J         SN74LS273N           SN74LS221N         SN74LS249N         SN74LS279AD           SN74LS22D         SN74LS24D         SN74LS279AFK           SN74LS22EK         SN74LS24J         SN74LS279AJ           SN74LS22J         SN74LS24N         SN74LS279AN           SN74LS22J         SN74LS24N         SN74LS27D           SN74LS22N         SN74LS251D         SN74LS27D           SN74LS240DW         SN74LS251FK         SN74LS27FK           SN74LS240FK         SN74LS251J         SN74LS27J           SN74LS240J         SN74LS251J         SN74LS27J           SN74LS240J         SN74LS253D         SN74LS280D           SN74LS240N         SN74LS253B         SN74LS280D           SN74LS241D         SN74LS253FK         SN74LS280FK           SN74LS241DW         SN74LS253B         SN74LS280J           SN74LS241DW         SN74LS257BD         SN74LS283D           SN74LS242D         SN74LS257BFK         SN74LS	SN74LS21D	SN74LS248D	SN74LS26FK
SN74LS21N         SN74LS248N         SN74LS273DW           SN74LS221D         SN74LS249D         SN74LS273FK           SN74LS221FK         SN74LS249FK         SN74LS273J           SN74LS221J         SN74LS249FK         SN74LS273N           SN74LS221D         SN74LS249D         SN74LS27AD           SN74LS22D         SN74LS24D         SN74LS279AFK           SN74LS22D         SN74LS24D         SN74LS279AFK           SN74LS22D         SN74LS24D         SN74LS279AFK           SN74LS22D         SN74LS24D         SN74LS279AFK           SN74LS22D         SN74LS24D         SN74LS27PAFK           SN74LS22D         SN74LS24D         SN74LS27PAFK           SN74LS22D         SN74LS24D         SN74LS27PAFK           SN74LS22D         SN74LS25D         SN74LS27PAFK           SN74LS24D         SN74LS25TFK         SN74LS27FK           SN74LS240D         SN74LS25TH         SN74LS280D           SN74LS241D         SN74LS25TH         SN74LS280FK           SN74LS241DW         SN74LS25TH         SN74LS280J           SN74LS241DW         SN74LS25TH         SN74LS280D           SN74LS241D         SN74LS25TH         SN74LS283D           SN74LS24D         SN74LS25TH         SN74	SN74LS21FK	SN74LS248FK	SN74LS26J
SN74LS221D         SN74LS249D         SN74LS273FK           SN74LS221FK         SN74LS249FK         SN74LS273J           SN74LS221J         SN74LS249J         SN74LS273N           SN74LS221N         SN74LS249N         SN74LS279AD           SN74LS22D         SN74LS24D         SN74LS279AFK           SN74LS22D         SN74LS24D         SN74LS279AJ           SN74LS22FK         SN74LS24J         SN74LS279AJ           SN74LS22J         SN74LS24N         SN74LS279AJ           SN74LS22J         SN74LS24N         SN74LS27PAJ           SN74LS22D         SN74LS251D         SN74LS27D           SN74LS24D         SN74LS251D         SN74LS27D           SN74LS240DW         SN74LS251FK         SN74LS27FK           SN74LS240FK         SN74LS251J         SN74LS27N           SN74LS240J         SN74LS253D         SN74LS280D           SN74LS240N         SN74LS253FK         SN74LS280FK           SN74LS241         SN74LS253F         SN74LS280F           SN74LS241FK         SN74LS253N         SN74LS280N           SN74LS241N         SN74LS257BD         SN74LS283D           SN74LS242D         SN74LS257BF         SN74LS283FK           SN74LS242PK         SN74LS258BD         SN74	SN74LS21J	SN74LS248J	SN74LS26N
SN74LS221FK         SN74LS249FK         SN74LS273J           SN74LS221J         SN74LS249J         SN74LS273N           SN74LS221N         SN74LS249N         SN74LS279AD           SN74LS22D         SN74LS24D         SN74LS279AFK           SN74LS2FK         SN74LS24J         SN74LS279AFK           SN74LS27BJ         SN74LS27PAJ           SN74LS22J         SN74LS24N         SN74LS27PAN           SN74LS22D         SN74LS251D         SN74LS27D           SN74LS22N         SN74LS251D         SN74LS27D           SN74LS240DW         SN74LS251FK         SN74LS27FK           SN74LS240FK         SN74LS251J         SN74LS27J           SN74LS240J         SN74LS251N         SN74LS27N           SN74LS240N         SN74LS253D         SN74LS280D           SN74LS241         SN74LS253FK         SN74LS280FK           SN74LS241DW         SN74LS253J         SN74LS280J           SN74LS241FK         SN74LS253N         SN74LS280D           SN74LS241N         SN74LS257BD         SN74LS283D           SN74LS242D         SN74LS257BFK         SN74LS283J           SN74LS242D         SN74LS257BD         SN74LS283J           SN74LS242D         SN74LS258BD         SN74LS28A      <	SN74LS21N	SN74LS248N	SN74LS273DW
SN74LS221J         SN74LS249J         SN74LS273N           SN74LS221N         SN74LS249N         SN74LS279AD           SN74LS22D         SN74LS24D         SN74LS279AFK           SN74LS22FK         SN74LS24J         SN74LS279AJ           SN74LS22J         SN74LS24N         SN74LS279AN           SN74LS22D         SN74LS24N         SN74LS27D           SN74LS22N         SN74LS251D         SN74LS27D           SN74LS240DW         SN74LS251FK         SN74LS27FK           SN74LS240FK         SN74LS251J         SN74LS27J           SN74LS240J         SN74LS251J         SN74LS27N           SN74LS240J         SN74LS253D         SN74LS280D           SN74LS240N         SN74LS253FK         SN74LS280FK           SN74LS241         SN74LS253FK         SN74LS280FK           SN74LS241DW         SN74LS253J         SN74LS280J           SN74LS241FK         SN74LS253N         SN74LS280N           SN74LS241N         SN74LS257BD         SN74LS283D           SN74LS242D         SN74LS257BFK         SN74LS283FK           SN74LS242J         SN74LS257BD         SN74LS283N           SN74LS243D         SN74LS258BD         SN74LS28D           SN74LS243D         SN74LS258BFK         SN	SN74LS221D	SN74LS249D	SN74LS273FK
SN74LS221N         SN74LS249N         SN74LS279AD           SN74LS22D         SN74LS24D         SN74LS279AFK           SN74LS22FK         SN74LS24J         SN74LS279AJ           SN74LS22J         SN74LS24N         SN74LS279AN           SN74LS22N         SN74LS251D         SN74LS27D           SN74LS240DW         SN74LS251FK         SN74LS27FK           SN74LS240FK         SN74LS251J         SN74LS27J           SN74LS240J         SN74LS251J         SN74LS27N           SN74LS240J         SN74LS251N         SN74LS27N           SN74LS240J         SN74LS253D         SN74LS20D           SN74LS240N         SN74LS253FK         SN74LS280D           SN74LS241         SN74LS253FK         SN74LS280FK           SN74LS241DW         SN74LS253J         SN74LS280J           SN74LS241FK         SN74LS253N         SN74LS280N           SN74LS241N         SN74LS257BD         SN74LS283D           SN74LS242D         SN74LS257BFK         SN74LS283FK           SN74LS242J         SN74LS257BN         SN74LS283N           SN74LS242N         SN74LS258BD         SN74LS28D           SN74LS243D         SN74LS258BFK         SN74LS28B           SN74LS243J         SN74LS258BN         SN	SN74LS221FK	SN74LS249FK	SN74LS273J
SN74LS22D         SN74LS24D         SN74LS279AFK           SN74LS22FK         SN74LS24J         SN74LS279AJ           SN74LS22J         SN74LS24N         SN74LS27PAN           SN74LS22N         SN74LS251D         SN74LS27D           SN74LS240DW         SN74LS251FK         SN74LS27FK           SN74LS240FK         SN74LS251J         SN74LS27J           SN74LS240F         SN74LS251N         SN74LS27N           SN74LS240J         SN74LS253D         SN74LS25N           SN74LS240N         SN74LS253D         SN74LS280D           SN74LS241         SN74LS253FK         SN74LS280FK           SN74LS241DW         SN74LS253J         SN74LS280J           SN74LS241FK         SN74LS253N         SN74LS280N           SN74LS241N         SN74LS257BD         SN74LS283D           SN74LS242D         SN74LS257BFK         SN74LS283FK           SN74LS242FK         SN74LS257BJ         SN74LS283J           SN74LS242J         SN74LS257BD         SN74LS283N           SN74LS243D         SN74LS258BD         SN74LS28BD           SN74LS243D         SN74LS258BFK         SN74LS28B           SN74LS243J         SN74LS258BN         SN74LS28N           SN74LS243N         SN74LS259BFK <td< td=""><td>SN74LS221J</td><td>SN74LS249J</td><td>SN74LS273N</td></td<>	SN74LS221J	SN74LS249J	SN74LS273N
SN74LS22FK         SN74LS24J         SN74LS279AJ           SN74LS22J         SN74LS24N         SN74LS279AN           SN74LS22N         SN74LS251D         SN74LS27D           SN74LS240DW         SN74LS251FK         SN74LS27FK           SN74LS240FK         SN74LS251J         SN74LS27J           SN74LS240F         SN74LS251N         SN74LS27J           SN74LS240J         SN74LS251N         SN74LS27N           SN74LS240N         SN74LS253D         SN74LS280D           SN74LS241         SN74LS253FK         SN74LS280FK           SN74LS241DW         SN74LS253J         SN74LS280J           SN74LS241FK         SN74LS253N         SN74LS280N           SN74LS241N         SN74LS257BD         SN74LS283D           SN74LS242D         SN74LS257BFK         SN74LS283FK           SN74LS242FK         SN74LS257BJ         SN74LS283J           SN74LS242I         SN74LS257BN         SN74LS283N           SN74LS242N         SN74LS258BD         SN74LS28BD           SN74LS243D         SN74LS258BFK         SN74LS28J           SN74LS243J         SN74LS258BN         SN74LS28N           SN74LS243J         SN74LS259BD         SN74LS290D           SN74LS244DW         SN74LS259BFK         <	SN74LS221N	SN74LS249N	SN74LS279AD
SN74LS22J         SN74LS24N         SN74LS279AN           SN74LS22N         SN74LS251D         SN74LS27D           SN74LS240DW         SN74LS251FK         SN74LS27FK           SN74LS240FK         SN74LS251J         SN74LS27J           SN74LS240J         SN74LS251N         SN74LS27N           SN74LS240N         SN74LS253D         SN74LS280D           SN74LS241         SN74LS253FK         SN74LS280FK           SN74LS241DW         SN74LS253J         SN74LS280J           SN74LS241FK         SN74LS253N         SN74LS280J           SN74LS241N         SN74LS257BD         SN74LS283D           SN74LS242D         SN74LS257BFK         SN74LS283FK           SN74LS242D         SN74LS257BJ         SN74LS283J           SN74LS242J         SN74LS257BN         SN74LS283J           SN74LS242D         SN74LS257BN         SN74LS283N           SN74LS243D         SN74LS258BD         SN74LS28D           SN74LS243D         SN74LS258BFK         SN74LS28J           SN74LS243J         SN74LS258BN         SN74LS28N           SN74LS243N         SN74LS259BD         SN74LS290D           SN74LS244DW         SN74LS259BFK         SN74LS290FK           SN74LS244FK         SN74LS259BJ	SN74LS22D	SN74LS24D	SN74LS279AFK
SN74LS22N         SN74LS251D         SN74LS27D           SN74LS240DW         SN74LS251FK         SN74LS27FK           SN74LS240FK         SN74LS251J         SN74LS27J           SN74LS240J         SN74LS251N         SN74LS27N           SN74LS240N         SN74LS253D         SN74LS280D           SN74LS241         SN74LS253FK         SN74LS280FK           SN74LS241DW         SN74LS253J         SN74LS280J           SN74LS241FK         SN74LS253N         SN74LS280N           SN74LS241N         SN74LS257BD         SN74LS283D           SN74LS242D         SN74LS257BFK         SN74LS283FK           SN74LS242D         SN74LS257BJ         SN74LS283J           SN74LS242FK         SN74LS257BJ         SN74LS283J           SN74LS242J         SN74LS257BN         SN74LS283N           SN74LS242N         SN74LS258BD         SN74LS28D           SN74LS243D         SN74LS258BFK         SN74LS28FK           SN74LS243J         SN74LS258BN         SN74LS28N           SN74LS243N         SN74LS259BD         SN74LS290D           SN74LS244DW         SN74LS259BFK         SN74LS290FK           SN74LS244FK         SN74LS259BJ         SN74LS290J	SN74LS22FK	SN74LS24J	SN74LS279AJ
SN74LS240DW         SN74LS251FK         SN74LS27FK           SN74LS240FK         SN74LS251J         SN74LS27J           SN74LS240J         SN74LS251N         SN74LS27N           SN74LS240N         SN74LS253D         SN74LS280D           SN74LS241         SN74LS253FK         SN74LS280FK           SN74LS241DW         SN74LS253J         SN74LS280J           SN74LS241FK         SN74LS253N         SN74LS280N           SN74LS241N         SN74LS257BD         SN74LS283D           SN74LS242D         SN74LS257BFK         SN74LS283FK           SN74LS242PK         SN74LS257BJ         SN74LS283J           SN74LS242J         SN74LS257BN         SN74LS283N           SN74LS242D         SN74LS257BN         SN74LS28N           SN74LS242J         SN74LS257BN         SN74LS283N           SN74LS243D         SN74LS258BFK         SN74LS28FK           SN74LS243FK         SN74LS258BN         SN74LS28N           SN74LS243J         SN74LS258BN         SN74LS28N           SN74LS243N         SN74LS259BD         SN74LS290D           SN74LS244FK         SN74LS259BJ         SN74LS290J	SN74LS22J	SN74LS24N	SN74LS279AN
SN74LS240FK         SN74LS251J         SN74LS27J           SN74LS240J         SN74LS251N         SN74LS27N           SN74LS240N         SN74LS253D         SN74LS280D           SN74LS241         SN74LS253FK         SN74LS280FK           SN74LS241DW         SN74LS253J         SN74LS280J           SN74LS241FK         SN74LS253N         SN74LS280N           SN74LS241N         SN74LS257BD         SN74LS283D           SN74LS242N         SN74LS257BFK         SN74LS283FK           SN74LS242FK         SN74LS257BJ         SN74LS283J           SN74LS242J         SN74LS257BN         SN74LS283N           SN74LS242N         SN74LS257BB         SN74LS28D           SN74LS243D         SN74LS258BFK         SN74LS28FK           SN74LS243FK         SN74LS258BJ         SN74LS28I           SN74LS243J         SN74LS258BN         SN74LS28N           SN74LS243N         SN74LS259BD         SN74LS290D           SN74LS244FK         SN74LS259BFK         SN74LS290FK           SN74LS244FK         SN74LS259BJ         SN74LS290J	SN74LS22N	SN74LS251D	SN74LS27D
SN74LS240J         SN74LS251N         SN74LS27N           SN74LS240N         SN74LS253D         SN74LS280D           SN74LS241         SN74LS253FK         SN74LS280FK           SN74LS241DW         SN74LS253J         SN74LS280J           SN74LS241FK         SN74LS253N         SN74LS280N           SN74LS241N         SN74LS257BD         SN74LS283D           SN74LS242D         SN74LS257BFK         SN74LS283FK           SN74LS242FK         SN74LS257BJ         SN74LS283J           SN74LS242J         SN74LS257BN         SN74LS283N           SN74LS242D         SN74LS257BN         SN74LS28N           SN74LS242D         SN74LS257BN         SN74LS283N           SN74LS242D         SN74LS258BD         SN74LS28N           SN74LS243D         SN74LS258BFK         SN74LS28FK           SN74LS243FK         SN74LS258BJ         SN74LS28J           SN74LS243J         SN74LS258BN         SN74LS28N           SN74LS243N         SN74LS259BD         SN74LS290D           SN74LS244FK         SN74LS259BJ         SN74LS290J	SN74LS240DW	SN74LS251FK	SN74LS27FK
SN74LS240N         SN74LS253D         SN74LS280D           SN74LS241         SN74LS253FK         SN74LS280FK           SN74LS241DW         SN74LS253J         SN74LS280J           SN74LS241FK         SN74LS253N         SN74LS280N           SN74LS241N         SN74LS257BD         SN74LS283D           SN74LS242D         SN74LS257BFK         SN74LS283FK           SN74LS242PK         SN74LS257BJ         SN74LS283J           SN74LS242J         SN74LS257BN         SN74LS283N           SN74LS242J         SN74LS257BD         SN74LS28D           SN74LS242N         SN74LS258BD         SN74LS28D           SN74LS243D         SN74LS258BFK         SN74LS28FK           SN74LS243FK         SN74LS258BJ         SN74LS28J           SN74LS243J         SN74LS258BN         SN74LS28N           SN74LS243N         SN74LS259BD         SN74LS290D           SN74LS244DW         SN74LS259BFK         SN74LS290FK           SN74LS244FK         SN74LS259BJ         SN74LS290J	SN74LS240FK	SN74LS251J	SN74LS27J
SN74LS241         SN74LS253FK         SN74LS280FK           SN74LS241DW         SN74LS253J         SN74LS280J           SN74LS241FK         SN74LS253N         SN74LS280N           SN74LS241N         SN74LS257BD         SN74LS283D           SN74LS242D         SN74LS257BFK         SN74LS283FK           SN74LS242FK         SN74LS257BJ         SN74LS283J           SN74LS242FK         SN74LS257BN         SN74LS283N           SN74LS242J         SN74LS257BN         SN74LS283N           SN74LS242N         SN74LS258BD         SN74LS28D           SN74LS243D         SN74LS258BFK         SN74LS28FK           SN74LS243FK         SN74LS258BJ         SN74LS28J           SN74LS243J         SN74LS258BN         SN74LS28N           SN74LS243N         SN74LS259BD         SN74LS290D           SN74LS244DW         SN74LS259BJ         SN74LS290FK           SN74LS244FK         SN74LS259BJ         SN74LS290J	SN74LS240J	SN74LS251N	SN74LS27N
SN74LS241DW         SN74LS253J         SN74LS280J           SN74LS241FK         SN74LS253N         SN74LS280N           SN74LS241N         SN74LS257BD         SN74LS283D           SN74LS242D         SN74LS257BFK         SN74LS283FK           SN74LS242FK         SN74LS257BJ         SN74LS283J           SN74LS242J         SN74LS257BN         SN74LS283N           SN74LS242D         SN74LS258BD         SN74LS28D           SN74LS243D         SN74LS258BFK         SN74LS28FK           SN74LS243FK         SN74LS258BJ         SN74LS28J           SN74LS243J         SN74LS258BN         SN74LS28N           SN74LS243N         SN74LS259BD         SN74LS290D           SN74LS244DW         SN74LS259BFK         SN74LS290FK           SN74LS244FK         SN74LS259BJ         SN74LS290J	SN74LS240N	SN74LS253D	SN74LS280D
SN74LS241FK         SN74LS253N         SN74LS280N           SN74LS241N         SN74LS257BD         SN74LS283D           SN74LS242D         SN74LS257BFK         SN74LS283FK           SN74LS242FK         SN74LS257BJ         SN74LS283J           SN74LS242J         SN74LS257BN         SN74LS283N           SN74LS242N         SN74LS258BD         SN74LS28D           SN74LS243D         SN74LS258BFK         SN74LS28FK           SN74LS243FK         SN74LS258BJ         SN74LS28J           SN74LS243J         SN74LS258BN         SN74LS28N           SN74LS243N         SN74LS259BD         SN74LS290D           SN74LS244DW         SN74LS259BFK         SN74LS290FK           SN74LS244FK         SN74LS259BJ         SN74LS290J	SN74LS241	SN74LS253FK	SN74LS280FK
SN74LS241N         SN74LS257BD         SN74LS283D           SN74LS242D         SN74LS257BFK         SN74LS283FK           SN74LS242FK         SN74LS257BJ         SN74LS283J           SN74LS242J         SN74LS257BN         SN74LS283N           SN74LS242N         SN74LS258BD         SN74LS28D           SN74LS243D         SN74LS258BFK         SN74LS28FK           SN74LS243FK         SN74LS258BJ         SN74LS28J           SN74LS243J         SN74LS258BN         SN74LS28N           SN74LS243N         SN74LS259BD         SN74LS290D           SN74LS244DW         SN74LS259BFK         SN74LS290FK           SN74LS244FK         SN74LS259BJ         SN74LS290J	SN74LS241DW	SN74LS253J	SN74LS280J
SN74LS242D         SN74LS257BFK         SN74LS283FK           SN74LS242FK         SN74LS257BJ         SN74LS283J           SN74LS242J         SN74LS257BN         SN74LS283N           SN74LS242N         SN74LS258BD         SN74LS28D           SN74LS243D         SN74LS258BFK         SN74LS28FK           SN74LS243FK         SN74LS258BJ         SN74LS28J           SN74LS243J         SN74LS258BN         SN74LS28N           SN74LS243N         SN74LS259BD         SN74LS290D           SN74LS244DW         SN74LS259BFK         SN74LS290FK           SN74LS244FK         SN74LS259BJ         SN74LS290J	SN74LS241FK	SN74LS253N	SN74LS280N
SN74LS242FK         SN74LS257BJ         SN74LS283J           SN74LS242J         SN74LS257BN         SN74LS283N           SN74LS242N         SN74LS258BD         SN74LS28D           SN74LS243D         SN74LS258BFK         SN74LS28FK           SN74LS243FK         SN74LS258BJ         SN74LS28J           SN74LS243J         SN74LS258BN         SN74LS28N           SN74LS243N         SN74LS259BD         SN74LS290D           SN74LS244DW         SN74LS259BFK         SN74LS290FK           SN74LS244FK         SN74LS259BJ         SN74LS290J	SN74LS241N	SN74LS257BD	SN74LS283D
SN74LS242J         SN74LS257BN         SN74LS283N           SN74LS242N         SN74LS258BD         SN74LS28D           SN74LS243D         SN74LS258BFK         SN74LS28FK           SN74LS243FK         SN74LS258BJ         SN74LS28J           SN74LS243J         SN74LS258BN         SN74LS28N           SN74LS243N         SN74LS259BD         SN74LS290D           SN74LS244DW         SN74LS259BFK         SN74LS290FK           SN74LS244FK         SN74LS259BJ         SN74LS290J	SN74LS242D	SN74LS257BFK	SN74LS283FK
SN74LS242N         SN74LS258BD         SN74LS28D           SN74LS243D         SN74LS258BFK         SN74LS28FK           SN74LS243FK         SN74LS258BJ         SN74LS28J           SN74LS243J         SN74LS258BN         SN74LS28N           SN74LS243N         SN74LS259BD         SN74LS290D           SN74LS244DW         SN74LS259BFK         SN74LS290FK           SN74LS244FK         SN74LS259BJ         SN74LS290J	SN74LS242FK	SN74LS257BJ	SN74LS283J
SN74LS243D         SN74LS258BFK         SN74LS28FK           SN74LS243FK         SN74LS258BJ         SN74LS28J           SN74LS243J         SN74LS258BN         SN74LS28N           SN74LS243N         SN74LS259BD         SN74LS290D           SN74LS244DW         SN74LS259BFK         SN74LS290FK           SN74LS244FK         SN74LS259BJ         SN74LS290J	SN74LS242J	SN74LS257BN	SN74LS283N
SN74LS243FK         SN74LS258BJ         SN74LS28J           SN74LS243J         SN74LS258BN         SN74LS28N           SN74LS243N         SN74LS259BD         SN74LS290D           SN74LS244DW         SN74LS259BFK         SN74LS290FK           SN74LS244FK         SN74LS259BJ         SN74LS290J	SN74LS242N	SN74LS258BD	SN74LS28D
SN74LS243J         SN74LS258BN         SN74LS28N           SN74LS243N         SN74LS259BD         SN74LS290D           SN74LS244DW         SN74LS259BFK         SN74LS290FK           SN74LS244FK         SN74LS259BJ         SN74LS290J	SN74LS243D	SN74LS258BFK	SN74LS28FK
SN74LS243N         SN74LS259BD         SN74LS290D           SN74LS244DW         SN74LS259BFK         SN74LS290FK           SN74LS244FK         SN74LS259BJ         SN74LS290J	SN74LS243FK	SN74LS258BJ	SN74LS28J
SN74LS244DW         SN74LS259BFK         SN74LS290FK           SN74LS244FK         SN74LS259BJ         SN74LS290J	SN74LS243J	SN74LS258BN	SN74LS28N
SN74LS244FK SN74LS259BJ SN74LS290J	SN74LS243N	SN74LS259BD	SN74LS290D
	SN74LS244DW	SN74LS259BFK	SN74LS290FK
SN74LS244J SN74LS259BN SN74LS290N	SN74LS244FK	SN74LS259BJ	SN74LS290J
	SN74LS244J	SN74LS259BN	SN74LS290N

Appendix A: Digital Integrated Circuits included in P-CAD Signal Integrity

SN74LS244N	SN74LS261D	SN74LS292FK
SN74LS245DW	SN74LS261FK	SN74LS292J
SN74LS245FK	SN74LS261J	SN74LS292N
SN74LS293D	SN74LS32FK	SN74LS365AFK
SN74LS293FK	SN74LS32J	SN74LS365AJ
SN74LS293J	SN74LS32N	SN74LS365AN
SN74LS293N	SN74LS33D	SN74LS366AD
SN74LS294FK	SN74LS33FK	SN74LS366AFK
SN74LS294J	SN74LS33J	SN74LS366AJ
SN74LS294N	SN74LS33N	SN74LS366AN
SN74LS295BD	SN74LS347D	SN74LS367AD
SN74LS295BFK	SN74LS347FK	SN74LS367AFK
SN74LS295BJ	SN74LS347J	SN74LS367AJ
SN74LS295BN	SN74LS347N	SN74LS367AN
SN74LS297D	SN74LS348D	SN74LS368AD
SN74LS297FK	SN74LS348FK	SN74LS368AFK
SN74LS297J	SN74LS348J	SN74LS368AJ
SN74LS297N	SN74LS348N	SN74LS368AN
SN74LS298D	SN74LS352D	SN74LS373DW
SN74LS298FK	SN74LS352FK	SN74LS373FK
SN74LS298J	SN74LS352J	SN74LS373J
SN74LS298N	SN74LS352N	SN74LS373N
SN74LS299DW	SN74LS353D	SN74LS374DW
SN74LS299FK	SN74LS353FK	SN74LS374FK
SN74LS299J	SN74LS353J	SN74LS374J
SN74LS299N	SN74LS353N	SN74LS374N
SN74LS30D	SN74LS354DW	SN74LS375D
SN74LS30FK	SN74LS354FK	SN74LS375FK
SN74LS30J	SN74LS354J	SN74LS375J
SN74LS30N	SN74LS354N	SN74LS375N
SN74LS31D	SN74LS355DW	SN74LS377DW
SN74LS31FK	SN74LS355FK	SN74LS377FK
SN74LS31J	SN74LS355J	SN74LS377J
-		

Appendix A: Digital Integrated Circuits included in P-CAD Signal Integrity

SN74LS31N         SN74LS355N         SN74LS377N           SN74LS322ADW         SN74LS356DW         SN74LS378D           SN74LS322AFK         SN74LS356FK         SN74LS378FK           SN74LS322AJ         SN74LS356FK         SN74LS378B           SN74LS322AN         SN74LS356N         SN74LS378N           SN74LS323DW         SN74LS357DW         SN74LS379D           SN74LS323BK         SN74LS357FK         SN74LS379D           SN74LS323J         SN74LS357FK         SN74LS379J           SN74LS323D         SN74LS357N         SN74LS379N           SN74LS32D         SN74LS357N         SN74LS37D           SN74LS37FK         SN74LS36AD         SN74LS37D           SN74LS37FK         SN74LS396FK         SN74LS443FK           SN74LS37I         SN74LS396FK         SN74LS443I           SN74LS37N         SN74LS396I         SN74LS443I           SN74LS381ADW         SN74LS398DW         SN74LS444DW           SN74LS381AFK         SN74LS398FK         SN74LS444FK           SN74LS381AJ         SN74LS398FK         SN74LS444FK           SN74LS382ADW         SN74LS399BW         SN74LS444D           SN74LS382ADW         SN74LS399FK         SN74LS445FK           SN74LS384D         SN74LS44			
SN74LS322AFK         SN74LS356FK         SN74LS378FK           SN74LS322AJ         SN74LS356J         SN74LS378J           SN74LS322AN         SN74LS356N         SN74LS378N           SN74LS323DW         SN74LS357DW         SN74LS379D           SN74LS323FK         SN74LS357FK         SN74LS379FK           SN74LS323J         SN74LS357J         SN74LS379J           SN74LS323N         SN74LS357N         SN74LS379D           SN74LS32D         SN74LS365AD         SN74LS37D           SN74LS37EK         SN74LS36FK         SN74LS37D           SN74LS37FK         SN74LS396FK         SN74LS43FK           SN74LS37J         SN74LS396J         SN74LS443FK           SN74LS37J         SN74LS396N         SN74LS443I           SN74LS381ADW         SN74LS39BDW         SN74LS444DW           SN74LS381AFK         SN74LS39BFK         SN74LS444FK           SN74LS381AJ         SN74LS39BI         SN74LS444J           SN74LS382ADW         SN74LS399D         SN74LS444D           SN74LS382AFK         SN74LS399FK         SN74LS445FK           SN74LS382AJ         SN74LS399N         SN74LS445N           SN74LS384D         SN74LS440D         SN74LS446D           SN74LS384AP         SN74LS440D </td <td>SN74LS31N</td> <td>SN74LS355N</td> <td>SN74LS377N</td>	SN74LS31N	SN74LS355N	SN74LS377N
SN74LS322AJ         SN74LS356J         SN74LS378J           SN74LS322AN         SN74LS356N         SN74LS378N           SN74LS323DW         SN74LS357DW         SN74LS379D           SN74LS323FK         SN74LS357FK         SN74LS379FK           SN74LS323J         SN74LS357J         SN74LS379J           SN74LS323N         SN74LS357N         SN74LS379N           SN74LS32D         SN74LS365AD         SN74LS37D           SN74LS37FK         SN74LS396FK         SN74LS43FK           SN74LS37J         SN74LS396J         SN74LS443J           SN74LS37N         SN74LS396N         SN74LS443N           SN74LS381ADW         SN74LS398DW         SN74LS444DW           SN74LS381AFK         SN74LS398FK         SN74LS444FK           SN74LS381AJ         SN74LS398J         SN74LS444FK           SN74LS381AJ         SN74LS398N         SN74LS444H           SN74LS382ADW         SN74LS399D         SN74LS445D           SN74LS382AJ         SN74LS399FK         SN74LS445FK           SN74LS382AJ         SN74LS399N         SN74LS445N           SN74LS384D         SN74LS40D         SN74LS446D           SN74LS384J         SN74LS40D         SN74LS46FK           SN74LS384J         SN74LS40J	SN74LS322ADW	SN74LS356DW	SN74LS378D
SN74LS322AN         SN74LS356N         SN74LS378N           SN74LS323DW         SN74LS357DW         SN74LS379D           SN74LS323FK         SN74LS357FK         SN74LS379FK           SN74LS323J         SN74LS357F         SN74LS379J           SN74LS323N         SN74LS357N         SN74LS379N           SN74LS32D         SN74LS365AD         SN74LS37D           SN74LS37FK         SN74LS396FK         SN74LS43FK           SN74LS37J         SN74LS396J         SN74LS443J           SN74LS37N         SN74LS396N         SN74LS443N           SN74LS381ADW         SN74LS398DW         SN74LS444DW           SN74LS381AFK         SN74LS398FK         SN74LS444FK           SN74LS381AJ         SN74LS398J         SN74LS444FK           SN74LS381AJ         SN74LS398N         SN74LS444J           SN74LS381AN         SN74LS399N         SN74LS444D           SN74LS382ADW         SN74LS399FK         SN74LS445FK           SN74LS382AJ         SN74LS399FK         SN74LS445FK           SN74LS382AJ         SN74LS399N         SN74LS445N           SN74LS384D         SN74LS40D         SN74LS446D           SN74LS384J         SN74LS40D         SN74LS446FK           SN74LS384N         SN74LS40J	SN74LS322AFK	SN74LS356FK	SN74LS378FK
SN74LS323DW         SN74LS357DW         SN74LS379D           SN74LS323FK         SN74LS357FK         SN74LS379FK           SN74LS323J         SN74LS357J         SN74LS379J           SN74LS323N         SN74LS357N         SN74LS379N           SN74LS32D         SN74LS36AD         SN74LS37D           SN74LS37FK         SN74LS36AD         SN74LS437D           SN74LS37FK         SN74LS396FK         SN74LS443FK           SN74LS37J         SN74LS396J         SN74LS443J           SN74LS37N         SN74LS396N         SN74LS443J           SN74LS37N         SN74LS396N         SN74LS443N           SN74LS381ADW         SN74LS398DW         SN74LS444DW           SN74LS381AFK         SN74LS398FK         SN74LS444FK           SN74LS381AJ         SN74LS398N         SN74LS444J           SN74LS381AN         SN74LS399D         SN74LS444N           SN74LS382ADW         SN74LS399FK         SN74LS445FK           SN74LS382AJ         SN74LS399FK         SN74LS445FK           SN74LS382AJ         SN74LS399N         SN74LS445N           SN74LS384D         SN74LS40D         SN74LS446D           SN74LS384FK         SN74LS40FK         SN74LS446FK           SN74LS384H         SN74LS440D	SN74LS322AJ	SN74LS356J	SN74LS378J
SN74LS323FK         SN74LS357FK         SN74LS379FK           SN74LS323J         SN74LS357J         SN74LS379J           SN74LS323N         SN74LS357N         SN74LS379N           SN74LS32D         SN74LS365AD         SN74LS37D           SN74LS37FK         SN74LS365AD         SN74LS443FK           SN74LS37FK         SN74LS396FK         SN74LS443FK           SN74LS37J         SN74LS396J         SN74LS443J           SN74LS37N         SN74LS396N         SN74LS443J           SN74LS381ADW         SN74LS398DW         SN74LS444DW           SN74LS381ADW         SN74LS398FK         SN74LS444FK           SN74LS381AJ         SN74LS398H         SN74LS444FK           SN74LS381AN         SN74LS398N         SN74LS444J           SN74LS382ADW         SN74LS399D         SN74LS445D           SN74LS382AFK         SN74LS399FK         SN74LS445FK           SN74LS382AJ         SN74LS399J         SN74LS445F           SN74LS384D         SN74LS399N         SN74LS445N           SN74LS384D         SN74LS40D         SN74LS446D           SN74LS384H         SN74LS40FK         SN74LS446FK           SN74LS384H         SN74LS40N         SN74LS446N           SN74LS385DW         SN74LS440N	SN74LS322AN	SN74LS356N	SN74LS378N
SN74LS323J         SN74LS357J         SN74LS379J           SN74LS323N         SN74LS357N         SN74LS379N           SN74LS32D         SN74LS365AD         SN74LS37D           SN74LS37FK         SN74LS366FK         SN74LS443FK           SN74LS37J         SN74LS396FK         SN74LS443J           SN74LS37J         SN74LS396J         SN74LS443J           SN74LS37N         SN74LS396N         SN74LS443N           SN74LS381ADW         SN74LS398DW         SN74LS444DW           SN74LS381AFK         SN74LS398FK         SN74LS444FK           SN74LS381AJ         SN74LS398J         SN74LS444F           SN74LS381AN         SN74LS398N         SN74LS444H           SN74LS382ADW         SN74LS399D         SN74LS445D           SN74LS382AFK         SN74LS399FK         SN74LS445FK           SN74LS382AJ         SN74LS399I         SN74LS445J           SN74LS382AN         SN74LS49D         SN74LS445N           SN74LS384D         SN74LS40D         SN74LS446D           SN74LS384H         SN74LS40FK         SN74LS446FK           SN74LS384N         SN74LS40D         SN74LS446N           SN74LS384N         SN74LS40D         SN74LS446FK           SN74LS384N         SN74LS40D	SN74LS323DW	SN74LS357DW	SN74LS379D
SN74LS323N         SN74LS357N         SN74LS379N           SN74LS32D         SN74LS365AD         SN74LS37D           SN74LS37FK         SN74LS396FK         SN74LS443FK           SN74LS37FK         SN74LS396FK         SN74LS443FK           SN74LS37D         SN74LS396FK         SN74LS443J           SN74LS37N         SN74LS396N         SN74LS443N           SN74LS381ADW         SN74LS398DW         SN74LS444DW           SN74LS381AFK         SN74LS398FK         SN74LS444FK           SN74LS381AJ         SN74LS398J         SN74LS444F           SN74LS381AN         SN74LS398N         SN74LS444N           SN74LS382ADW         SN74LS399D         SN74LS445D           SN74LS382AFK         SN74LS399FK         SN74LS445FK           SN74LS382AJ         SN74LS399I         SN74LS445N           SN74LS382AN         SN74LS49D         SN74LS445N           SN74LS384D         SN74LS40D         SN74LS446D           SN74LS384I         SN74LS40D         SN74LS446FK           SN74LS384I         SN74LS40D         SN74LS446N           SN74LS384N         SN74LS40D         SN74LS446N           SN74LS385DW         SN74LS422D         SN74LS446N           SN74LS385DW         SN74LS422I	SN74LS323FK	SN74LS357FK	SN74LS379FK
SN74LS32D         SN74LS36AD         SN74LS37D           SN74LS37FK         SN74LS396FK         SN74LS443FK           SN74LS37J         SN74LS396J         SN74LS443J           SN74LS37N         SN74LS396N         SN74LS443N           SN74LS381ADW         SN74LS398DW         SN74LS444DW           SN74LS381AFK         SN74LS398FK         SN74LS444FK           SN74LS381AJ         SN74LS398J         SN74LS444FK           SN74LS381AJ         SN74LS398J         SN74LS444J           SN74LS381AN         SN74LS398N         SN74LS444J           SN74LS382ADW         SN74LS399D         SN74LS445D           SN74LS382AFK         SN74LS399FK         SN74LS445FK           SN74LS382AJ         SN74LS399J         SN74LS445J           SN74LS382AN         SN74LS399N         SN74LS445N           SN74LS384D         SN74LS40D         SN74LS446D           SN74LS384FK         SN74LS40FK         SN74LS446FK           SN74LS384J         SN74LS40FK         SN74LS446FK           SN74LS384N         SN74LS40N         SN74LS446N           SN74LS384N         SN74LS40N         SN74LS446FK           SN74LS384N         SN74LS40N         SN74LS446N           SN74LS384N         SN74LS422D	SN74LS323J	SN74LS357J	SN74LS379J
SN74LS37FK         SN74LS396FK         SN74LS443FK           SN74LS37J         SN74LS396J         SN74LS443J           SN74LS37N         SN74LS396N         SN74LS443N           SN74LS381ADW         SN74LS398DW         SN74LS444DW           SN74LS381AFK         SN74LS398FK         SN74LS444FK           SN74LS381AJ         SN74LS398FK         SN74LS444FK           SN74LS381AJ         SN74LS398J         SN74LS444J           SN74LS381AJ         SN74LS398N         SN74LS444J           SN74LS381AN         SN74LS398N         SN74LS444D           SN74LS382ADW         SN74LS399D         SN74LS445D           SN74LS382AFK         SN74LS399FK         SN74LS445FK           SN74LS382AJ         SN74LS399J         SN74LS445J           SN74LS384D         SN74LS40D         SN74LS446D           SN74LS384FK         SN74LS40FK         SN74LS446FK           SN74LS384J         SN74LS40J         SN74LS446FK           SN74LS384N         SN74LS40N         SN74LS446N           SN74LS384N         SN74LS40N         SN74LS446N           SN74LS384N         SN74LS420D         SN74LS446N           SN74LS385DW         SN74LS422D         SN74LS447D           SN74LS385FK         SN74LS422J	SN74LS323N	SN74LS357N	SN74LS379N
SN74LS37J         SN74LS396J         SN74LS443J           SN74LS37N         SN74LS396N         SN74LS443N           SN74LS381ADW         SN74LS398DW         SN74LS444DW           SN74LS381AFK         SN74LS398FK         SN74LS444FK           SN74LS381AJ         SN74LS398J         SN74LS444FK           SN74LS381AJ         SN74LS398J         SN74LS444J           SN74LS381AN         SN74LS398N         SN74LS444J           SN74LS382ADW         SN74LS399D         SN74LS445D           SN74LS382AFK         SN74LS399FK         SN74LS445FK           SN74LS382AJ         SN74LS399J         SN74LS445J           SN74LS382AN         SN74LS399N         SN74LS445N           SN74LS384D         SN74LS40D         SN74LS446D           SN74LS384FK         SN74LS40FK         SN74LS446FK           SN74LS384J         SN74LS40J         SN74LS446F           SN74LS384N         SN74LS40N         SN74LS446D           SN74LS384N         SN74LS40N         SN74LS446N           SN74LS385DW         SN74LS422D         SN74LS447D           SN74LS385FK         SN74LS422FK         SN74LS447J           SN74LS385N         SN74LS422D         SN74LS447N           SN74LS386AD         SN74LS423D	SN74LS32D	SN74LS365AD	SN74LS37D
SN74LS37N         SN74LS396N         SN74LS443N           SN74LS381ADW         SN74LS398DW         SN74LS444DW           SN74LS381AFK         SN74LS398FK         SN74LS444FK           SN74LS381AJ         SN74LS398J         SN74LS444FK           SN74LS381AN         SN74LS398N         SN74LS444N           SN74LS382ADW         SN74LS399D         SN74LS445D           SN74LS382AFK         SN74LS399FK         SN74LS445FK           SN74LS382AJ         SN74LS399J         SN74LS445J           SN74LS382AN         SN74LS399N         SN74LS445N           SN74LS384D         SN74LS40D         SN74LS446D           SN74LS384FK         SN74LS40FK         SN74LS446FK           SN74LS384J         SN74LS40J         SN74LS446FK           SN74LS384N         SN74LS40N         SN74LS446FK           SN74LS385DW         SN74LS42D         SN74LS447D           SN74LS385FK         SN74LS422FK         SN74LS447FK           SN74LS385N         SN74LS422D         SN74LS447N           SN74LS386AD         SN74LS423D         SN74LS448DW           SN74LS386AFK         SN74LS423FK         SN74LS448FK           SN74LS386AJ         SN74LS423J         SN74LS448J	SN74LS37FK	SN74LS396FK	SN74LS443FK
SN74LS381ADW         SN74LS398DW         SN74LS444DW           SN74LS381AFK         SN74LS398FK         SN74LS444FK           SN74LS381AJ         SN74LS398J         SN74LS444J           SN74LS381AN         SN74LS398N         SN74LS444N           SN74LS382ADW         SN74LS399D         SN74LS445D           SN74LS382AFK         SN74LS399FK         SN74LS445FK           SN74LS382AJ         SN74LS399J         SN74LS445J           SN74LS382AN         SN74LS399N         SN74LS445N           SN74LS384D         SN74LS40D         SN74LS446D           SN74LS384FK         SN74LS40FK         SN74LS446FK           SN74LS384J         SN74LS40J         SN74LS446FK           SN74LS384N         SN74LS40N         SN74LS446N           SN74LS385DW         SN74LS422D         SN74LS447D           SN74LS385FK         SN74LS422FK         SN74LS447FK           SN74LS385N         SN74LS422N         SN74LS447N           SN74LS386AD         SN74LS423D         SN74LS448DW           SN74LS386AJ         SN74LS423J         SN74LS448J	SN74LS37J	SN74LS396J	SN74LS443J
SN74LS381AFK         SN74LS398FK         SN74LS444FK           SN74LS381AJ         SN74LS398J         SN74LS444J           SN74LS381AN         SN74LS398N         SN74LS444N           SN74LS382ADW         SN74LS399D         SN74LS445D           SN74LS382AFK         SN74LS399FK         SN74LS445FK           SN74LS382AJ         SN74LS399J         SN74LS445J           SN74LS382AN         SN74LS399N         SN74LS445N           SN74LS384D         SN74LS40D         SN74LS446D           SN74LS384FK         SN74LS40FK         SN74LS446FK           SN74LS384J         SN74LS40J         SN74LS446J           SN74LS384N         SN74LS40N         SN74LS446N           SN74LS385DW         SN74LS42D         SN74LS447D           SN74LS385FK         SN74LS422FK         SN74LS447FK           SN74LS385N         SN74LS422N         SN74LS447N           SN74LS386AD         SN74LS423FK         SN74LS448FK           SN74LS386AFK         SN74LS423FK         SN74LS448FK           SN74LS448J         SN74LS448J	SN74LS37N	SN74LS396N	SN74LS443N
SN74LS381AJ         SN74LS398J         SN74LS444J           SN74LS381AN         SN74LS398N         SN74LS444N           SN74LS382ADW         SN74LS399D         SN74LS445D           SN74LS382AFK         SN74LS399FK         SN74LS445FK           SN74LS382AJ         SN74LS399J         SN74LS445J           SN74LS382AN         SN74LS399N         SN74LS445J           SN74LS384D         SN74LS40D         SN74LS446D           SN74LS384FK         SN74LS40FK         SN74LS446FK           SN74LS384J         SN74LS40J         SN74LS446J           SN74LS384N         SN74LS40N         SN74LS446N           SN74LS385DW         SN74LS422D         SN74LS447D           SN74LS385FK         SN74LS422FK         SN74LS447FK           SN74LS385N         SN74LS422N         SN74LS447N           SN74LS386AD         SN74LS423D         SN74LS448DW           SN74LS386AJ         SN74LS423J         SN74LS448FK           SN74LS448J         SN74LS448J         SN74LS448J	SN74LS381ADW	SN74LS398DW	SN74LS444DW
SN74LS381AN         SN74LS398N         SN74LS444N           SN74LS382ADW         SN74LS399D         SN74LS445D           SN74LS382AFK         SN74LS399FK         SN74LS445FK           SN74LS382AJ         SN74LS399J         SN74LS445J           SN74LS382AN         SN74LS399N         SN74LS445N           SN74LS384D         SN74LS40D         SN74LS446D           SN74LS384FK         SN74LS40FK         SN74LS446FK           SN74LS384J         SN74LS40J         SN74LS446J           SN74LS384N         SN74LS40N         SN74LS446N           SN74LS385DW         SN74LS422D         SN74LS447D           SN74LS385FK         SN74LS422FK         SN74LS447FK           SN74LS385J         SN74LS422J         SN74LS447N           SN74LS386AD         SN74LS423D         SN74LS447N           SN74LS386AFK         SN74LS423FK         SN74LS448FK           SN74LS386AJ         SN74LS423J         SN74LS448J	SN74LS381AFK	SN74LS398FK	SN74LS444FK
SN74LS382ADW         SN74LS399D         SN74LS445D           SN74LS382AFK         SN74LS399FK         SN74LS445FK           SN74LS382AJ         SN74LS399J         SN74LS445J           SN74LS382AN         SN74LS399N         SN74LS445N           SN74LS384D         SN74LS40D         SN74LS446D           SN74LS384FK         SN74LS40FK         SN74LS446FK           SN74LS384J         SN74LS40J         SN74LS446J           SN74LS384N         SN74LS40N         SN74LS446N           SN74LS385DW         SN74LS422D         SN74LS447D           SN74LS385FK         SN74LS422FK         SN74LS447FK           SN74LS385J         SN74LS422J         SN74LS447J           SN74LS385N         SN74LS422N         SN74LS447N           SN74LS386AD         SN74LS423D         SN74LS448DW           SN74LS386AFK         SN74LS423FK         SN74LS448FK           SN74LS448J         SN74LS448J         SN74LS448J	SN74LS381AJ	SN74LS398J	SN74LS444J
SN74LS382AFK         SN74LS399FK         SN74LS445FK           SN74LS382AJ         SN74LS399J         SN74LS445J           SN74LS382AN         SN74LS399N         SN74LS445N           SN74LS384D         SN74LS40D         SN74LS446D           SN74LS384FK         SN74LS40FK         SN74LS446FK           SN74LS384J         SN74LS40J         SN74LS446J           SN74LS384N         SN74LS40N         SN74LS446N           SN74LS385DW         SN74LS42D         SN74LS447D           SN74LS385FK         SN74LS422FK         SN74LS447FK           SN74LS385J         SN74LS422J         SN74LS447J           SN74LS385N         SN74LS422N         SN74LS447N           SN74LS386AD         SN74LS423D         SN74LS448DW           SN74LS386AFK         SN74LS423FK         SN74LS448FK           SN74LS386AJ         SN74LS423J         SN74LS448J	SN74LS381AN	SN74LS398N	SN74LS444N
SN74LS382AJ         SN74LS399J         SN74LS445J           SN74LS382AN         SN74LS399N         SN74LS445N           SN74LS384D         SN74LS40D         SN74LS446D           SN74LS384FK         SN74LS40FK         SN74LS446FK           SN74LS384J         SN74LS40J         SN74LS446J           SN74LS384N         SN74LS40N         SN74LS446N           SN74LS385DW         SN74LS422D         SN74LS447D           SN74LS385FK         SN74LS422FK         SN74LS447FK           SN74LS385J         SN74LS422J         SN74LS447J           SN74LS385N         SN74LS422N         SN74LS447N           SN74LS386AD         SN74LS423D         SN74LS448DW           SN74LS386AFK         SN74LS423FK         SN74LS448FK           SN74LS386AJ         SN74LS423J         SN74LS448J	SN74LS382ADW	SN74LS399D	SN74LS445D
SN74LS382AN         SN74LS399N         SN74LS445N           SN74LS384D         SN74LS40D         SN74LS446D           SN74LS384FK         SN74LS40FK         SN74LS446FK           SN74LS384J         SN74LS40J         SN74LS446J           SN74LS384N         SN74LS40N         SN74LS446N           SN74LS385DW         SN74LS422D         SN74LS447D           SN74LS385FK         SN74LS422FK         SN74LS447FK           SN74LS385J         SN74LS422J         SN74LS447J           SN74LS385N         SN74LS422N         SN74LS447N           SN74LS386AD         SN74LS423D         SN74LS448DW           SN74LS386AFK         SN74LS423FK         SN74LS448FK           SN74LS386AJ         SN74LS423J         SN74LS448J	SN74LS382AFK	SN74LS399FK	SN74LS445FK
SN74LS384D         SN74LS40D         SN74LS446D           SN74LS384FK         SN74LS40FK         SN74LS446FK           SN74LS384J         SN74LS40J         SN74LS446J           SN74LS384N         SN74LS40N         SN74LS446N           SN74LS385DW         SN74LS422D         SN74LS447D           SN74LS385FK         SN74LS422FK         SN74LS447FK           SN74LS385J         SN74LS422J         SN74LS447J           SN74LS385N         SN74LS422N         SN74LS447N           SN74LS386AD         SN74LS423D         SN74LS448DW           SN74LS386AFK         SN74LS423FK         SN74LS448FK           SN74LS386AJ         SN74LS423J         SN74LS448J	SN74LS382AJ	SN74LS399J	SN74LS445J
SN74LS384FK         SN74LS40FK         SN74LS446FK           SN74LS384J         SN74LS40J         SN74LS446J           SN74LS384N         SN74LS40N         SN74LS446N           SN74LS385DW         SN74LS422D         SN74LS447D           SN74LS385FK         SN74LS422FK         SN74LS447FK           SN74LS385J         SN74LS422J         SN74LS447J           SN74LS385N         SN74LS422N         SN74LS447N           SN74LS386AD         SN74LS423D         SN74LS448DW           SN74LS386AFK         SN74LS423FK         SN74LS448FK           SN74LS386AJ         SN74LS423J         SN74LS448J	SN74LS382AN	SN74LS399N	SN74LS445N
SN74LS384J         SN74LS40J         SN74LS446J           SN74LS384N         SN74LS40N         SN74LS446N           SN74LS385DW         SN74LS422D         SN74LS447D           SN74LS385FK         SN74LS422FK         SN74LS447FK           SN74LS385J         SN74LS422J         SN74LS447J           SN74LS385N         SN74LS422N         SN74LS447N           SN74LS386AD         SN74LS423D         SN74LS448DW           SN74LS386AFK         SN74LS423FK         SN74LS448FK           SN74LS386AJ         SN74LS423J         SN74LS448J	SN74LS384D	SN74LS40D	SN74LS446D
SN74LS384N         SN74LS440N         SN74LS446N           SN74LS385DW         SN74LS422D         SN74LS447D           SN74LS385FK         SN74LS422FK         SN74LS447FK           SN74LS385J         SN74LS422J         SN74LS447J           SN74LS385N         SN74LS422N         SN74LS447N           SN74LS386AD         SN74LS423D         SN74LS448DW           SN74LS386AFK         SN74LS423FK         SN74LS448FK           SN74LS386AJ         SN74LS423J         SN74LS448J	SN74LS384FK	SN74LS40FK	SN74LS446FK
SN74LS385DW         SN74LS422D         SN74LS447D           SN74LS385FK         SN74LS422FK         SN74LS447FK           SN74LS385J         SN74LS422J         SN74LS447J           SN74LS385N         SN74LS422N         SN74LS447N           SN74LS386AD         SN74LS423D         SN74LS448DW           SN74LS386AFK         SN74LS423FK         SN74LS448FK           SN74LS386AJ         SN74LS423J         SN74LS448J	SN74LS384J	SN74LS40J	SN74LS446J
SN74LS385FK         SN74LS422FK         SN74LS447FK           SN74LS385J         SN74LS422J         SN74LS447J           SN74LS385N         SN74LS422N         SN74LS447N           SN74LS386AD         SN74LS423D         SN74LS448DW           SN74LS386AFK         SN74LS423FK         SN74LS448FK           SN74LS386AJ         SN74LS423J         SN74LS448J	SN74LS384N	SN74LS40N	SN74LS446N
SN74LS385J         SN74LS422J         SN74LS447J           SN74LS385N         SN74LS422N         SN74LS447N           SN74LS386AD         SN74LS423D         SN74LS448DW           SN74LS386AFK         SN74LS423FK         SN74LS448FK           SN74LS386AJ         SN74LS423J         SN74LS448J	SN74LS385DW	SN74LS422D	SN74LS447D
SN74LS385N         SN74LS422N         SN74LS447N           SN74LS386AD         SN74LS423D         SN74LS448DW           SN74LS386AFK         SN74LS423FK         SN74LS448FK           SN74LS386AJ         SN74LS423J         SN74LS448J	SN74LS385FK	SN74LS422FK	SN74LS447FK
SN74LS386AD         SN74LS423D         SN74LS448DW           SN74LS386AFK         SN74LS423FK         SN74LS448FK           SN74LS386AJ         SN74LS423J         SN74LS448J	SN74LS385J	SN74LS422J	SN74LS447J
SN74LS386AFK         SN74LS423FK         SN74LS448FK           SN74LS386AJ         SN74LS423J         SN74LS448J	SN74LS385N	SN74LS422N	SN74LS447N
SN74LS386AJ SN74LS423J SN74LS448J	SN74LS386AD	SN74LS423D	SN74LS448DW
	SN74LS386AFK	SN74LS423FK	SN74LS448FK
	SN74LS386AJ	SN74LS423J	SN74LS448J
SN74LS386AN SN74LS423N SN74LS448N	SN74LS386AN	SN74LS423N	SN74LS448N

Appendix A: Digital Integrated Circuits included in P-CAD Signal Integrity

SN74LS38D	SN74LS42D	SN74LS449D
SN74LS38FK	SN74LS42FK	SN74LS449FK
SN74LS38J	SN74LS42J	SN74LS449J
SN74LS38N	SN74LS42N	SN74LS449N
SN74LS390D	SN74LS440DW	SN74LS465DW
SN74LS390FK	SN74LS440FK	SN74LS465FK
SN74LS390J	SN74LS440J	SN74LS465J
SN74LS390N	SN74LS440N	SN74LS465N
SN74LS393D	SN74LS441DW	SN74LS466DW
SN74LS393FK	SN74LS441FK	SN74LS466FK
SN74LS393J	SN74LS441J	SN74LS466J
SN74LS393N	SN74LS441N	SN74LS466N
SN74LS395AD	SN74LS442DW	SN74LS467DW
SN74LS395AFK	SN74LS442FK	SN74LS467FK
SN74LS395AJ	SN74LS442J	SN74LS467J
SN74LS395AN	SN74LS442N	SN74LS467N
SN74LS396D	SN74LS443DW	SN74LS468DW
SN74LS468FK	SN74LS56P	SN74LS600AN
SN74LS468J	SN74LS57JG	SN74LS601ADW
SN74LS468N	SN74LS57P	SN74LS601AJ
SN74LS47D	SN74LS589FK	SN74LS601AN
SN74LS47FK	SN74LS589J	SN74LS602ADW
SN74LS47J	SN74LS589N	SN74LS602AJ
SN74LS47N	SN74LS590FK	SN74LS602AN
SN74LS48D	SN74LS590J	SN74LS603ADW
SN74LS48FK	SN74LS590N	SN74LS603AJ
SN74LS48J	SN74LS591FK	SN74LS603AN
SN74LS48N	SN74LS591J	SN74LS604FK
SN74LS490D	SN74LS591N	SN74LS604JD
SN74LS490FK	SN74LS592FK	SN74LS604N
SN74LS490J	SN74LS592J	SN74LS605FK
SN74LS490N	SN74LS592N	SN74LS605JD
SN74LS49D	SN74LS593DW	SN74LS605N

Appendix A: Digital Integrated Circuits included in P-CAD Signal Integrity

SN74LS49FK	SN74LS593FK	SN74LS606FK
SN74LS49J	SN74LS593J	SN74LS606JD
SN74LS49N	SN74LS593N	SN74LS606N
SN74LS51D	SN74LS594FK	SN74LS607FK
SN74LS51FK	SN74LS594J	SN74LS607JD
SN74LS51J	SN74LS594N	SN74LS607N
SN74LS51N	SN74LS595FK	SN74LS608D
SN74LS540DW	SN74LS595J	SN74LS608FK
SN74LS540FK	SN74LS595N	SN74LS608J
SN74LS540J	SN74LS596FK	SN74LS608N
SN74LS540N	SN74LS596J	SN74LS610JD
SN74LS541DW	SN74LS596N	SN74LS610N
SN74LS541FK	SN74LS597FK	SN74LS611JD
SN74LS541J	SN74LS597J	SN74LS611N
SN74LS541N	SN74LS597N	SN74LS612JD
SN74LS54D	SN74LS598DW	SN74LS612N
SN74LS54FK	SN74LS598FK	SN74LS613JD
SN74LS54J	SN74LS598J	SN74LS613N
SN74LS54N	SN74LS598N	SN74LS620DW
SN74LS55D	SN74LS599FK	SN74LS620FK
SN74LS55FK	SN74LS599J	SN74LS620J
SN74LS55J	SN74LS599N	SN74LS620N
SN74LS55N	SN74LS600ADW	SN74LS621DW
SN74LS56JG	SN74LS600AJ	SN74LS621FK
SN74LS621J	SN74LS641DW	SN74LS652DW
SN74LS621N	SN74LS641FK	SN74LS652FK
SN74LS622DW	SN74LS641J	SN74LS652JT
SN74LS622FK	SN74LS641N	SN74LS652NT
SN74LS622J	SN74LS642DW	SN74LS653DW
SN74LS622N	SN74LS642FK	SN74LS653FK
SN74LS623DW	SN74LS642J	SN74LS653JT
SN74LS623FK	SN74LS642N	SN74LS653NT
SN74LS623J	SN74LS643DW	SN74LS654DW

Appendix A: Digital Integrated Circuits included in P-CAD Signal Integrity

SN74LS623N	SN74LS643FK	SN74LS654FK
SN74LS630Fk	SN74LS643J	SN74LS654JT
SN74LS630JD	SN74LS643N	SN74LS654NT
SN74LS630N	SN74LS644DW	SN74LS668D
SN74LS631FK	SN74LS644FK	SN74LS668FK
SN74LS631JD	SN74LS644J	SN74LS668J
SN74LS631N	SN74LS644N	SN74LS668N
SN74LS636DW	SN74LS645DW	SN74LS669D
SN74LS636FK	SN74LS645FK	SN74LS669FK
SN74LS636J	SN74LS645J	SN74LS669J
SN74LS636N	SN74LS645N	SN74LS669N
SN74LS637DW	SN74LS646DW	SN74LS670D
SN74LS637FK	SN74LS646FK	SN74LS670FK
SN74LS637J	SN74LS646JT	SN74LS670J
SN74LS637N	SN74LS646NT	SN74LS670N
SN74LS638DW	SN74LS647DW	SN74LS671DW
SN74LS638FK	SN74LS647FK	SN74LS671FK
SN74LS638J	SN74LS647JT	SN74LS671J
SN74LS638N	SN74LS647NT	SN74LS671N
SN74LS639DW	SN74LS648DW	SN74LS672DW
SN74LS639FK	SN74LS648FK	SN74LS672FK
SN74LS639J	SN74LS648JT	SN74LS672J
SN74LS639N	SN74LS648NT	SN74LS672N
SN74LS63D	SN74LS649DW	SN74LS673DW
SN74LS63FK	SN74LS649FK	SN74LS673FK
SN74LS63J	SN74LS649JT	SN74LS673J
SN74LS63N	SN74LS649NT	SN74LS673N
SN74LS640DW	SN74LS651DW	SN74LS674DW
SN74LS640FK	SN74LS651FK	SN74LS674FK
SN74LS640J	SN74LS651JT	SN74LS674J
SN74LS640N	SN74LS651NT	SN74LS674N
SN74LS681DW	SN74LS690DW	SN74LS74AFK
SN74LS681FK	SN74LS690FK	SN74LS74AJ

Appendix A: Digital Integrated Circuits included in P-CAD Signal Integrity

SN74LS681J	SN74LS690J	SN74LS74AN
SN74LS681N	SN74LS690N	SN74LS75D
SN74LS682DW	SN74LS691DW	SN74LS75J
SN74LS682FK	SN74LS691FK	SN74LS75N
SN74LS682J	SN74LS691J	SN74LS76AD
SN74LS682N	SN74LS691N	SN74LS76AJ
SN74LS683DW	SN74LS692DW	SN74LS76AN
SN74LS683FK	SN74LS692FK	SN74LS78AD
SN74LS683J	SN74LS692J	SN74LS78AJ
SN74LS683N	SN74LS692N	SN74LS78AN
SN74LS684DW	SN74LS693DW	SN74LS83AD
SN74LS684FK	SN74LS693FK	SN74LS83AFK
SN74LS684J	SN74LS693J	SN74LS83AJ
SN74LS684N	SN74LS693N	SN74LS83AN
SN74LS685DW	SN74LS696DW	SN74LS85D
SN74LS685FK	SN74LS696FK	SN74LS85FK
SN74LS685J	SN74LS696J	SN74LS85J
SN74LS685N	SN74LS696N	SN74LS85N
SN74LS686DW	SN74LS697DW	SN74LS86AD
SN74LS686FK	SN74LS697FK	SN74LS86AFK
SN74LS686JT	SN74LS697J	SN74LS86AJ
SN74LS686NT	SN74LS697N	SN74LS86AN
SN74LS687DW	SN74LS698DW	SN74LS90D
SN74LS687FK	SN74LS698FK	SN74LS90J
SN74LS687JT	SN74LS698J	SN74LS90N
SN74LS687NT	SN74LS698N	SN74LS91D
SN74LS688DW	SN74LS699DW	SN74LS91J
SN74LS688FK	SN74LS699FK	SN74LS91N
SN74LS688J	SN74LS699J	SN74LS92D
SN74LS688N	SN74LS699N	SN74LS92J
SN74LS689DW	SN74LS69D	SN74LS92N
SN74LS689FK	SN74LS69FK	SN74LS93D
SN74LS689J	SN74LS69J	SN74LS93J

Appendix A: Digital Integrated Circuits included in P-CAD Signal Integrity

SN74LS689N	SN74LS69N	SN74LS93N
SN74LS68D	SN74LS73AD	SN74LS95BD
SN74LS68FK	SN74LS73AJ	SN74LS95BFK
SN74LS68J	SN74LS73AN	SN74LS95BJ
SN74LS68N	SN74LS74AD	SN74LS95BN
SN74LS96D	SN74LV273DW	SN74LVC125PW
SN74LS96J	SN74LV273PW	SN74LVC126D
SN74LS96N	SN74LV32D	SN74LVC126DB
SN74LV00D	SN74LV32DB	SN74LVC126PW
SN74LV00DB	SN74LV32PW	SN74LVC137DB
SN74LV00PW	SN74LV373DB	SN74LVC137DW
SN74LV02D	SN74LV373DW	SN74LVC137PW
SN74LV02DB	SN74LV373PW	SN74LVC138DB
SN74LV02PW	SN74LV374DB	SN74LVC138DW
SN74LV04D	SN74LV374DW	SN74LVC138PW
SN74LV04DB	SN74LV374PW	SN74LVC139DB
SN74LV04PW	SN74LV573DB	SN74LVC139DW
SN74LV08D	SN74LV573DW	SN74LVC139PW
SN74LV08DB	SN74LV573PW	SN74LVC14D
SN74LV08PW	SN74LV574DB	SN74LVC14DB
SN74LV125D	SN74LV574DW	SN74LVC14PW
SN74LV125DB	SN74LV574PW	SN74LVC157DB
SN74LV125PW	SN74LV74D	SN74LVC157DW
SN74LV138D	SN74LV74DB	SN74LVC157PW
SN74LV138DB	SN74LV74PW	SN74LVC158DB
SN74LV138PW	SN74LVC00D	SN74LVC158DW
SN74LV14D	SN74LVC00DB	SN74LVC158PW
SN74LV14DB	SN74LVC00PW	SN74LVC16240DGG
SN74LV14PW	SN74LVC02D	SN74LVC16240DL
SN74LV164D	SN74LVC02DB	SN74LVC16241DGG
SN74LV164DB	SN74LVC02PW	SN74LVC16241DL
SN74LV164PW	SN74LVC04D	SN74LVC16244DGG
SN74LV174D	SN74LVC04DB	SN74LVC16244DL

Appendix A: Digital Integrated Circuits included in P-CAD Signal Integrity

SN74LV174DB	SN74LVC04PW	SN74LVC16245DGG
SN74LV174PW	SN74LVC08D	SN74LVC16245DL
SN74LV240DB	SN74LVC08DB	SN74LVC16373DGG
SN74LV240DW	SN74LVC08PW	SN74LVC16373DL
SN74LV240PW	SN74LVC10D	SN74LVC16374DGG
SN74LV244DB	SN74LVC10DB	SN74LVC16374DL
SN74LV244DW	SN74LVC10PW	SN74LVC16540DGG
SN74LV244PW	SN74LVC112DB	SN74LVC16540DL
SN74LV245DB	SN74LVC112DW	SN74LVC16541DGG
SN74LV245DW	SN74LVC112PW	SN74LVC16541DL
SN74LV245PW	SN74LVC125D	SN74LVC16543DGG
SN74LV273DB	SN74LVC125DB	SN74LVC16543DL
SN74LVC16646DGG	SN74LVC540PW	SN74LVC843DB
SN74LVC16646DL	SN74LVC541DB	SN74LVC843DW
SN74LVC16652DGG	SN74LVC541DW	SN74LVC843PW
SN74LVC16652DL	SN74LVC541PW	SN74LVC861DB
SN74LVC16952DGG	SN74LVC543DB	SN74LVC861DW
SN74LVC16952DL	SN74LVC543DW	SN74LVC861PW
SN74LVC240DB	SN74LVC543PW	SN74LVC863DB
SN74LVC240DW	SN74LVC544DB	SN74LVC863DW
SN74LVC240PW	SN74LVC544DW	SN74LVC863PW
SN74LVC241DB	SN74LVC544PW	SN74LVC86D
SN74LVC241DW	SN74LVC573DB	SN74LVC86DB
SN74LVC241PW	SN74LVC573DW	SN74LVC86PW
SN74LVC244DB	SN74LVC573PW	SN74LVCU04D
SN74LVC244DW	SN74LVC574DB	SN74LVCU04DB
SN74LVC244PW	SN74LVC574DW	SN74LVCU04PW
SN74LVC245DB	SN74LVC574PW	SN74LVT125DB
SN74LVC245DW	SN74LVC646DB	SN74LVT125DW
SN74LVC245PW	SN74LVC646DW	SN74LVT125PW
SN74LVC257DB	SN74LVC646PW	SN74LVT162244DGG
SN74LVC257PW	SN74LVC652DB	SN74LVT162244DL
SN74LVC258DB	SN74LVC652DW	SN74LVT162245DGG
	•	•

Appendix A: Digital Integrated Circuits included in P-CAD Signal Integrity

SN74LVC258DW	SN74LVC652PW	SN74LVT162245DL
SN74LVC258PW	SN74LVC74D	SN74LVT162373DGG
SN74LVC2952DB	SN74LVC74DB	SN74LVT162373DL
SN74LVC2952DW	SN74LVC74PW	SN74LVT162374DGG
SN74LVC2952PW	SN74LVC821DB	SN74LVT162374DL
SN74LVC32D	SN74LVC821DW	SN74LVT16244ADGG
SN74LVC32DB	SN74LVC821PW	SN74LVT16244ADL
SN74LVC32PW	SN74LVC823DB	SN74LVT16245DGG
SN74LVC373DB	SN74LVC823DW	SN74LVT16245DL
SN74LVC373DW	SN74LVC823PW	SN74LVT16373DGG
SN74LVC373PW	SN74LVC827DB	SN74LVT16373DL
SN74LVC374DB	SN74LVC827DW	SN74LVT16374DGG
SN74LVC374DW	SN74LVC827PW	SN74LVT16374DL
SN74LVC374PW	SN74LVC828DB	SN74LVT16500DGG
SN74LVC4245DB	SN74LVC828DW	SN74LVT16500DL
SN74LVC4245DW	SN74LVC828PW	SN74LVT16501DGG
SN74LVC4245PW	SN74LVC841DB	SN74LVT16501DL
SN74LVC540DB	SN74LVC841DW	SN74LVT16543DGG
SN74LVC540DW	SN74LVC841PW	SN74LVT16543DL
SN74LVT16646DGG	SN74LVT652DW	SN74S09J
SN74LVT16646DL	SN74LVT652PW	SN74S09N
SN74LVT16652DGG	SN74LVTZ240DB	SN74S10D
SN74LVT16652DL	SN74LVTZ240DW	SN74S10FK
SN74LVT16952DGG	SN74LVTZ240PW	SN74S10J
SN74LVT18245DGG	SN74LVTZ244DB	SN74S10N
SN74LVT18245DL	SN74LVTZ244DW	SN74S112AD
SN74LVT18502PM	SN74LVTZ244PW	SN74S112AFK
SN74LVT18504PM	SN74LVTZ245DB	SN74S112AJ
SN74LVT240DB	SN74LVTZ245DW	SN74S112AN
SN74LVT240DW	SN74LVTZ245PW	SN74S113AD
SN74LVT240PW	SN74LVU04D	SN74S113AFK
SN74LVT241DB	SN74LVU04DB	SN74S113AJ
SN74LVT241DW	SN74LVU04PW	SN74S113AN

Appendix A: Digital Integrated Circuits included in P-CAD Signal Integrity

SN74LVT241PW	SN74S00D	SN74S114AD
SN74LVT244ADB	SN74S00FK	SN74S114AFK
SN74LVT244ADW	SN74S00J	SN74S114AJ
SN74LVT244APW	SN74S00N	SN74S114AN
SN74LVT245DB	SN74S02D	SN74S11D
SN74LVT245DW	SN74S02FK	SN74S11FK
SN74LVT245PW	SN74S02J	SN74S11J
SN74LVT273DB	SN74S02N	SN74S11N
SN74LVT273DW	SN74S03D	SN74S132D
SN74LVT273PW	SN74S03FK	SN74S132FK
SN74LVT2952DB	SN74S03J	SN74S132J
SN74LVT2952DW	SN74S03N	SN74S132N
SN74LVT2952PW	SN74S04D	SN74S133D
SN74LVT543DB	SN74S04FK	SN74S133FK
SN74LVT543DW	SN74S04J	SN74S133J
SN74LVT543PW	SN74S04N	SN74S133N
SN74LVT573DB	SN74S05D	SN74S134D
SN74LVT573DW	SN74S05FK	SN74S134FK
SN74LVT573PW	SN74S05J	SN74S134J
SN74LVT574DB	SN74S05N	SN74S134N
SN74LVT574DW	SN74S08D	SN74S135D
SN74LVT574PW	SN74S08FK	SN74S135FK
SN74LVT646DB	SN74S08J	SN74S135J
SN74LVT646DW	SN74S08N	SN74S135N
SN74LVT646PW	SN74S09D	SN74S138AD
SN74LVT652DB	SN74S09FK	SN74S138AFK
SN74S138AJ	SN74S168J	SN74S20J
SN74S138AN	SN74S168N	SN74S20N
SN74S139AD	SN74S169D	SN74S22D
SN74S139AFK	SN74S169FK	SN74S22FK
SN74S139AJ	SN74S169J	SN74S22J
SN74S139AN	SN74S169N	SN74S22N
SN74S140D	SN74S174D	SN74S240DW

Appendix A: Digital Integrated Circuits included in P-CAD Signal Integrity

SN74S140FK	SN74S174FK	SN74S240FK
SN74S140J	SN74S174J	SN74S240J
SN74S140N	SN74S174N	SN74S240N
SN74S151D	SN74S175D	SN74S241DW
SN74S151FK	SN74S175FK	SN74S241FK
SN74S151J	SN74S175J	SN74S241J
SN74S151N	SN74S175N	SN74S241N
SN74S153D	SN74S181DW	SN74S244DW
SN74S153FK	SN74S181FK	SN74S244FK
SN74S153J	SN74S181J	SN74S244J
SN74S153N	SN74S181N	SN74S244N
SN74S157D	SN74S182D	SN74S251D
SN74S157FK	SN74S182FK	SN74S251FK
SN74S157J	SN74S182J	SN74S251J
SN74S157N	SN74S182N	SN74S251N
SN74S158D	SN74S194D	SN74S253D
SN74S158FK	SN74S194FK	SN74S253FK
SN74S158J	SN74S194J	SN74S253J
SN74S158N	SN74S194N	SN74S253N
SN74S15D	SN74S195D	SN74S257D
SN74S15FK	SN74S195FK	SN74S257FK
SN74S15J	SN74S195J	SN74S257J
SN74S15N	SN74S195N	SN74S257N
SN74S162D	SN74S196D	SN74S258D
SN74S162FK	SN74S196FK	SN74S258FK
SN74S162J	SN74S196J	SN74S258J
SN74S162N	SN74S196N	SN74S258N
SN74S163D	SN74S197D	SN74S260D
SN74S163FK	SN74S197FK	SN74S260FK
SN74S163J	SN74S197J	SN74S260J
SN74S163N	SN74S197N	SN74S260N
SN74S168D	SN74S20D	SN74S280D
		<u> </u>

Appendix A: Digital Integrated Circuits included in P-CAD Signal Integrity

SN74S280J	SN74S40J	TIBPAL16R4-10CJ
SN74S280N	SN74S40N	TIBPAL16R4-10CN
SN74S283D	SN74S412DW	TIBPAL16R4-15CFN
SN74S283FK	SN74S412FK	TIBPAL16R4-15CJ
SN74S283J	SN74S412J	TIBPAL16R4-15CN
SN74S283N	SN74S412N	TIBPAL16R4-7CFN
SN74S299DW	SN74S51D	TIBPAL16R4-7CJ
SN74S299FK	SN74S51FK	TIBPAL16R4-7CN
SN74S299J	SN74S51J	TIBPAL16R6-10CFN
SN74S299N	SN74S51N	TIBPAL16R6-10CJ
SN74S30D	SN74S64D	TIBPAL16R6-10CN
SN74S30FK	SN74S64FK	TIBPAL16R6-15CFN
SN74S30J	SN74S64J	TIBPAL16R6-15CJ
SN74S30N	SN74S64N	TIBPAL16R6-15CN
SN74S32D	SN74S65D	TIBPAL16R6-7CFN
SN74S32FK	SN74S65FK	TIBPAL16R6-7CJ
SN74S32J	SN74S65J	TIBPAL16R6-7CN
SN74S32N	SN74S65N	TIBPAL16R8-10CFN
SN74S373DW	SN74S74D	TIBPAL16R8-10CJ
SN74S373FK	SN74S74FK	TIBPAL16R8-10CN
SN74S373J	SN74S74J	TIBPAL16R8-15CFN
SN74S373N	SN74S74N	TIBPAL16R8-15CJ
SN74S374DW	SN74S85D	TIBPAL16R8-15CN
SN74S374FK	SN74S85FK	TIBPAL16R8-7CFN
SN74S374J	SN74S85J	TIBPAL16R8-7CJ
SN74S374N	SN74S85N	TIBPAL16R8-7CN
SN74S37D	SN74S86D	TIBPAL20L8-10CFN
SN74S37FK	SN74S86FK	TIBPAL20L8-10CJT
SN74S37J	SN74S86J	TIBPAL20L8-10CNT
SN74S37N	SN74S86N	TIBPAL20L8-15CFN
SN74S381DW	TIBPAL16L8-10CFN	TIBPAL20L8-15CJT
SN74S381FK	TIBPAL16L8-10CJ	TIBPAL20L8-15CNT
SN74S381J	TIBPAL16L8-10CN	TIBPAL20L8-7CFN

Appendix A: Digital Integrated Circuits included in P-CAD Signal Integrity

TIBPAL16L8-15CFN	TIBPAL20L8-7CJT
TIBPAL16L8-15CJ	TIBPAL20L8-7CNT
TIBPAL16L8-15CN	TIBPAL20R4-10CFN
TIBPAL16L8-7CFN	TIBPAL20R4-10CJT
TIBPAL16L8-7CJ	TIBPAL20R4-10CNT
TIBPAL16L8-7CN	TIBPAL20R4-15CFN
TIBPAL16R4-10CFN	TIBPAL20R4-15CJT
TIBPAL20R6-15CJT	TIBPAL20R8-10CNT
TIBPAL20R6-15CNT	TIBPAL20R8-15CFN
TIBPAL20R6-7CFN	TIBPAL20R8-15CJT
TIBPAL20R6-7CJT	TIBPAL20R8-15CNT
TIBPAL20R6-7CNT	TIBPAL20R8-7CFN
TIBPAL20R8-10CFN	TIBPAL20R8-7CJT
TIBPAL20R8-10CJT	TIBPAL20R8-7CNT
	TIBPAL16L8-15CJ TIBPAL16L8-15CN TIBPAL16L8-7CFN TIBPAL16L8-7CJ TIBPAL16L8-7CN TIBPAL16R4-10CFN TIBPAL20R6-15CJT TIBPAL20R6-7CFN TIBPAL20R6-7CFN TIBPAL20R6-7CJT TIBPAL20R6-7CJT TIBPAL20R6-7CNT TIBPAL20R8-10CFN

# **List of Signal Integrity System Messages**

This appendix documents the messages that you might encounter when you use P-CAD Signal Integrity.

The messages are organized in three sections:

- 1. Signal Integrity System Messages
- 2. Wave Analyzer System Messages
- 3. P-CAD IBIS Converter System Messages

## **Signal Integrity System Messages**

Message	Cause	Solution
Cannot create project directory	This could mean that the P-CAD Signal Integrity directory is readonly.	Make sure that the P-CAD Signal Integrity directory is not read-only.
Error reading file: <filename></filename>	A syntax error was encountered during the load of a SULTAN file.	Check the file that it is a correct SULTAN file.
Cannot load licensing information. Please re-run SETUP.EXE	The license is not installed correctly.	Re-run the SETUP.EXE located on the P-CAD Signal Integrity installation CD.
Cannot locate program <pre><pre><pre><pre>cprogram name</pre>. Please re- run SETUP.EXE</pre></pre></pre>	The application cannot find a program that is necessary for the correct functionality.	Re-run the SETUP.EXE located on the P-CAD Signal Integrity installation CD.
Cannot initialize library module. Please re-run SETUP.EXE	This could mean that the library is deleted or the P-CAD Signal Integrity directory is read-only.	Re-run the SETUP.EXE located on the P-CAD-Signal Integrity installation CD.
DC Operation point not found. Check the nets and the simulator options and	Unmatched line terminations produce a lot of ringing.	Change the Simulator options for DC Analysis.

## Appendix B: Signal Integrity System Messages

Message	Cause	Solution
try again.		
Equation for the calculation of the line currents cannot be solved.	Transmission line loop in the net.	Re-design the net without any transmission line loop.
Internal time step too small. Check the nets and the simulator options and try again.	Numerical problems in solve the network equations.	Reduce the accuracy of the solution.
Simulation Error. Check the nets and try again.	The simulator generates an error message.	Check the nets.

## **Wave Analyzer Messages List**

Message	Cause	Solution
Cannot open file <filename></filename>	The input file does not exist.	Check for an existing input file.
Invalid input file <filename></filename>	A syntax error was encountered during the load of the input file.	Check the file that it is a correct input file.
Value out of bounds	One of the values is out of the range -1.0e-30 1.0e30	Enter appropriate value.
Cannot calculate the base line for a horizontal wave.	The program cannot calculate the base line for the current visible range of the selected wave.	Change display to include the base horizontal section of the wave.
Cannot calculate the top line for a horizontal wave.	The program cannot calculate the top line for the current visible range of the selected wave.	Change display to include the top horizontal section of the wave.
Cannot find values for top- and base-line.	The program cannot calculate the top- and base-line.	Inappropriate measurement tool has been chosen.
No ascending wave flank in the given range.	Cannot calculate the rise time, because the selected wave has no ascending wave flank.	Inappropriate measurement tool has been chosen.
No descending wave flank in the given range.	Cannot calculate the fall time, because the selected wave has no descending wave flank.	Inappropriate measurement tool has been chosen.
Cannot open file for output: <filename></filename>	The system is trying to open for writing a read-only file.	Make sure that the specified file is not a read-only file.

# P-CAD IBIS Converter System Messages

Message	Model library could not be initialized!
	You will not be able to generate any models!
Possible reasons	Model library non-existent/accessible or in wrong place
	Model library damaged
Туре	Warning
Occurrence	Converter Program Start
Cause	The converter program could not find the Model library. This may be reasoned by:
	passing an invalid library path to the converter on startup
	the model library is not existent or in wrong place
	the model library is damaged
Consequence	You cannot generate any models because there is no library to write them to.
Solution	If you started P-CAD IBIS Converter from outside P-CAD Signal Integrity, ensure that the parameter -lib < libpath > was passed where < libpath > is the path to the Signal Integrity library, which is: \P-CAD 2002\Lib.
	If you started P-CAD IBIS Converter from inside P-CAD Signal Integrity or if you could not fix this problem for the case described above, you must reinstall P-CAD Signal Integrity.

Message	Loading IBIS File failed!
Туре	Error
Occurrence	Loading an IBIS file
Cause	The IBIS file to be opened was not existent or could not be parsed correctly.
Consequence	You cannot use the IBIS file.
Solution	Contact device manufacturer for updated IBIS model.

Message	Invalid Model Name Syntax!
Туре	Error
Occurrence	Editing the model name of a buffer
Cause	Syntax of model name was invalid. You may only use standard identifier

## Appendix B: P-CAD IBIS Converter System Messages

	syntax for model names, which is:	
	name must with an alphabetic character or a '_'	
	name may only contain alphanumeric characters or '_'	
Consequence	The model name has not been changed.	
Solution	Retry and enter a valid model name.	

Message	Model Name too long (20-char. max.)!		
Туре	Error		
Occurrence	Editing the model name of a buffer		
Cause	Model name was too long.		
Consequence	The model name has not been changed.		
Solution	Retry and enter a model name using a maximum of 20 characters.		

Message	The following models already exist in the library: [model name list]
	These models will be overwritten if you continue. You may avoid this by aborting the export now, re-name the affected models and then export again.
	Do you really want to overwrite the existing models?
Туре	Warning
Occurrence	Exporting models to the library
Cause	The models listed already exist in the library.
	Reasons for this can be that you exported the same models or other models with the same names before or that other non-IBIS models in the library, which were created with the macromodel editor already use that names.
Consequence	You must decide between aborting your action or overwriting the existing models in the library.
Solution	If you are sure that you want to overwrite the listed models (e.g. because you exported them before, changed some parameters now and want to rewrite the models to the library) press the <b>Yes</b> button.
	If you are unsure and do not know anything about the models you would over-write, press the <b>No</b> button, re-name the affected models and retry exporting.

# APPENDIX C

# **Units and Default Values**

This appendix explains the units of measure used and their range and lists the default values used throughout P-CAD Signal Integrity.

## **Units Representation**

When you edit values for resistance, capacitance, time, length, temperature or whatever you may specify as follows:

Value type	Example (Voltage)	Result
Integer	13	13 V
Pointed decimal	3.65	3.65 V
Exponential form	4.2e-2	42 mV
Unit factor char.	8 k	8 kV
Unit factor char. and unit	5300 mV	5.3 V

## **Common Unit Factor Characters**

Character	Name	Factor
f	fento	10e-15
р	pico	10e-12
n	nano	10e-9
u	micro	10e-6
m	milli	10e-3
-	-	1

### Appendix C: Common Units

Character	Name	Factor
k	kilo	10e+3
М	mega	10e+6
G	giga	10e+9
Т	terra	10e+12

You cannot use unit factor characters where it is unusual, e.g. on temperature, time, angle.

## **Common Units**

Description	Unit	Unit name
Length	m	Meter
Time	S	Second
Voltage	V	Volt
Current	A	Ampere
Resistance	Ohm	Ohm
Inductance	Н	Henry
Capacitance	F	Farad
Angle		Degree
Temperature	С	Degree Celsius
Temperature	F	Farenheit
Temperature	K	Kelvin

## **Editor Parameter Descriptions**

Infinite Values (+inf) have been substituted by a value of 1000 within the application.

Resistor(arrays)By default there is one connection (pin 1-pin2) using a value of 1 MOhm.Inductor(arrays)By default there is one connection (pin 1-pin2) using a value of 10 nH.Capacitor(arrays)By default there is one connection (pin 1-pin2) using a value of 10 pF.

## IC - INPUT, TRISTATE - Basic

Name	Default	Description
Technology	-	technology
Supply Voltage	5 V	supply voltage
Resistance	1 Mohm	resistance
Capacitance	4 pF	capacitance

## IC - INPUT, TRISTATE - Clamping

Name	Default	Description
Power Voltage	5 V	power clamping voltage
Power dV/dI	50 Ohm	power clamping characteristic
GND Voltage	0 V	GND clamping voltage
GND dV/dI	50 Ohm	GND clamping characteristic

## IC - OUTPUT - Basic

Name	Default	Description
Technology	-	technology
Supply Voltage	5 V	supply voltage
Resistance Low	74.6 Ohm	resistance when signal is at a low level
Resistance High	57.1 Ohm	resistance when signal is at a high level
Capacitance	10 pF	capacitance

## IC - OUTPUT - Clamping

Name	Default	Description
Power Voltage	5 V	power clamping voltage
Power dV/dI	50 Ohm	power clamping characteristic
GND Voltage	0 V	GND clamping voltage
GND dV/dI	50 Ohm	GND clamping characteristic

## IC - OUTPUT - Voltage/Timing

Name	Default	Description
Voltage High	5 V	high level voltage
Voltage Low	0 V	low level voltage
Rise Time	3 ns	rising flank time
Fall Time	3.6 ns	falling flank time

## Appendix C: Editor Parameter Descriptions

Checking the Open Sink Box enables these parameters but disables Voltage Hi from the Voltage/Timing parameters!

### IC - OUTPUT - Open Sink

Name	Default	Description
Pull-up Resistance	220 Ohm	Pull-up resistance used for parameter determination
Pull-up Voltage	5 V	Pull-up voltage used for parameter determination

### **CONNECTOR - TRANSMISSION LINE**

Alias	Default	Description
C1	1 pF	line capacitance 1
C2	1 pF	line capacitance 2
ZL	57 Ohm	line impedance
td	125 ps	line delay time
I	18 mm	line length

By default there is a connector consisting of three lumped elements.

### **CONNECTOR - LUMPED ELEMENT**

Alias	Default	Description
CA1	600 fF	element capacitance A1
L1	700 pH	element inductance 1
CB1	500 fF	element capacitance B1
CA2	500 fF	element capacitance A2
L2	3.3 nH	element inductance 2
CB2	500 fF	element capacitance B2
CA3	600 fF	element capacitance A3
L3	3.3 nH	element inductance 3
CB3	600 fF	element capacitance B3

#### DIODE

For more information on diode parameters please consult a SPICE reference.

#### **Junction DC**

Alias	Default	Description
IS	10 fA	reverse saturation current

Alias	Default	Description
RS	0 Ohm	path resistance (ohmic series resistance)
N	1	emission coefficient
BV	+inf V	reverse breakdown voltage
IBV	1 kA	current at breakdown voltage

## **Junction Capacitance**

Alias	Default	Description
TT	0 s	transit time
CJO	0 F	zero-bias junction capacitance per unit function bottom wall
VJ	1 V	area junction contact potential
М	0.5	area junction grading coefficient

## **Temperature Effect**

Alias	Default	Description
EG	1.11 V	energy gap for p-n junction diode
XTI	3	saturation current temperature exponent

#### Noise

Alias	Default	Description
KF	0	flicker noise coefficient
AF	1	flicker noise exponent

## **Bipolar Junction Transistor (BJT) - NPN, PNP**

For more information on BJT parameters, please consult a SPICE reference.

### **Basic DC Model**

Alias	Default	Description
IS	0.1 fA	transport saturation current
BF	100	ideal maximum forward BETA
NF	1	forward current emission coefficient
BR	1	ideal maximum reverse BETA
NR	1	reverse current emission coefficient

#### **Base Width Modulation**

Alias	Default	Description
VAF	+inf V	forward early voltage

## Appendix C: Editor Parameter Descriptions

Alias	Default	Description
VAR	+inf V	reverse early voltage

## **High Current BETA Degradation Effect**

Alias	Default	Description
IKF	+inf A	corner forward BETA high current roll-off
IKR	+inf A	corner for reverse BETA high current roll-off

## **Low Current BETA Degradation Effect**

Alias	Default	Description
ISE	0 A	base-emitter saturation current
NE	1.5	base-emitter leakage saturation coefficient
ISC	0 A	base-collector leakage saturation current
NC	2	base-collector leakage emission coefficient
IBFL	0 A	forward base current at low level
IBRL	0 A	reverse base current at low level

## **Parasitic Resistor**

Alias	Default	Description
RB	0 Ohm	base resistance
IRB	+inf A	base current, where base resistance falls half way to RBM
RBM	RB	minimum high current base resistance
RE	0 Ohm	emitter resistance
RC	0 Ohm	collector resistance

## **Junction Capacitor**

Alias	Default	Description
CJE	0 F	base-emitter zero-bias depletion capacitance
VJE	750 mV	base-emitter built-in potential
MJE	0.33	base-emitter junction exponent (grading factor)
CJC	0 F	base-collector zero-bias depletion capacitance
VJC	750 mV	base-collector built-in potential
MJC	0.33	base-collector junction exponent (grading factor)
XCJC	1	internal base fraction of base-collector depletion capacitance
CJS	0 F	zero-bias collector-substrate capacitance

Alias	Default	Description
VJS	750 mV	substrate junction built-in potential
MJS	0	substrate junction exponent (grading factor)
FC	0.5	coefficient for forward-bias depletion periphery capacitance formula

## **Transit Time**

Alias	Default	Description
TF	0 s	base forward transit time
XTF	0	TF bias dependence coefficient
VTF	+inf	TF base-collector voltage dependence coefficient
ITF	0 A	TF high current parameter
PTF	0 Degree	frequency multiplier to determine excess phase
TR	0 s	base reverse transit time

## **Temperature Effect**

Alias	Default	Description
XTB	0	forward and reverse BETA temperature coefficient
EG	1.11 V	energy gap for p-n junction
XTI	3	saturation current temperature coefficient
T_NOM	27 Celsius	temperature at parameter determination

## Noise

Alias	Default	Description
KF	0	flicker noise coefficient
AF	1	flicker noise exponent

# Index

<b>-A</b> -	types	12, 52
Accessing Signal Integrity6	-E-	
Altium IBIS Converter	Edit	
System messages list171	component specifications	17. 53
Altium PCB	Designator	
database49	Designator specifications	
databases44	Layer Stack	
Receiving the DRC error indicator32	Layer stack specifications	
Altium PRO Route 2/42	menu	
Altium Xtalk76	Supply Nets	
D	Supply nets specifications	
-B-	Take Over	
Buffer data	Edit Buffer Data	
changing the stimulus18	model	54
loading the stimulus from a file19	stimulus	75
model screen18	stimulus load from a file	55
window for resistors20	stimulus pattern	55
-C-	stimulus save to a file	
•	window	54
Common units174	Edit commands	48
Components Specifications	Editor parameter description	
edit53	Base width modulation	177
Create a Macromodel	Bipolar junction transistor	177
from an IBIS file39	Connector - Transmission Line	176
tutorial example36	Diode	176
Crosstalk	IC input, triatate - clamping	175
introduction to76	IC output - basic	175
simulation76	IC output - clamping	175
simulation results76	IC output - Voltage / Timing	175
starting a simulation76	Junction capacitance	177
Crosstalk Data	Junction capacitor	178
report46	Junction DC	176
-D-	Low current BETA degradation e	effect 178
_	Noise	
Designator	Parasitic Resistor	178
edit51	Temperature effect	177, 179

### Index

Transit time	179	-L-	
Editor parameter specification		Layer stack	
High current BETA degradation effe		edit window	14
Editor parameters descriptions		parameter defaults	
Exit	48	Layer Stack	
-F-		parameters default values	50
File		parameters saved	
Get Nets	44	report	
Open		specifications	
Reports		transmission line parameters	
SULTAN Out		window	
File Menu		Library commands	93
File.commands		Basic library	
		Import IBIS file1	
-G-		menu	
General commands	93	searching the library	
Library commands		User library	
Macromodel editor		-М-	
Options commands		-171-	
Generate model report		Macromodel editor	
tutorial example	41	accessing the	
		BJT transistor models1	
-H-		Capacitors model1	
hardware requirements	5	Connector (Lumped element) model 1	
Help commands	119	Connector (Transmission line) model 1	
<b>-I</b> -		Diode models1	
		Edit add1	
IBIS files		Edit close1	
definition		Edit commands1	
exit		Edit delete1	
File commands		Edit open1	
File export		Edit save1	
File menu		Edit save as1	_
File open		establishing connections	
File report	114	File commands1	
model generation	110	IBIS model	
Strong case		IC clamping window	
Typical case		IC models96,	
Weak case		IC technology window	
report example		Inductors edit window1	
Import IBIS file		library tree description	
Info, Route	109	Resistance and Capacitance window	/9 ۱۵۵
Installation and Setup	•	Resistors model	
installing P-CAD products		User library	
system requirements	5	Window gassada	
		Window cascade	
		Window commands1	110

Window next	111	Report Voltage data	59
Macromodel editors		Save to an SDF file	
Inductors model	100	Timing view	
NI		View arrange nets	
-N-		View commands	
Net		View select columns	
characteristic impedance	49	Voltage view	
length			
screening		-0-	
Net Data		Options commands	115
report	46	menu	
Net simplify		Net simplify	
Nets		Simulator	
details displayed	16	Simulator accuracy	
Nets Screening		Simulator DC analysis	
description	57	Simulator integration	
Edit commands			117
edit delete		-P-	
edit invert selection		PCB design parameters	
edit menu		review and complete	11
edit select all		· _	1 1
		-R-	
File close		Reflection	
file commands		Introduction to the simulator	26
File Report		simulation	
Help commands		simulation results	
Help topics		starting a simulation	
Impedance view		Reflection simulation	/ J
Net Data view		introduction to	75
Report comma-separated			
Report date		results	26
Report destination		Reports	4.4
Report file extension		create	
Report filename		Date	
Report format	61	destination	
Report Impedance data	59	Destination	
Report Net data	58	File extensions	
Report Options	58	File save	
Report page footer	60	Filename	
Report page format	60	filename default	
Report page header	60	Footer	
Report page numbers		Format	
Report pagination		Header	
Report spreadsheet-loadable		Line per page	47
Report style		Net data	
Report Timing data		Net Screening file extensions	58
Report to file		Nets Screening	57
Report to screen		Nets Screening filename	58
		Nets Screening options	
		~ .	

### Index

Options	45	icons	43
Crosstalk Data	46	interface	6
Layer Stack	45	introduction to the simulator	69
Net Data	46	List of digital circuits included	122
output	44	menu bar	7, 43
Page	47	starting-up	10
page format		System messages	
Page format		System messages list	
Pagination		Toolbar	
spreadsheet-loadable		Tutorial	9
Style		Tutorial steps	9
to file		Units and default values	
to printer	47	Wave Analyzer	
to screen		Simulation '	
Reports Format		Crosstalk	76
Comma-Separated	47	menu	
Route		Reflection	75
Info	109	Set Aggressor Net	
Route Autorouters		Set Victim Net	
Run Crosstalk simulation		Termination Advisor	
tutorial example	33	Simulation commands	
Run Reflection simulation		Simulator	
_	<b>2</b> 0, 30	Accuracy options	117
<b>-S-</b>		DC analysis options	
saving a wave	28	input	
Screen the nets		Integration option	
Screening		options	
arrange nets by	25	save settings	
Impedance view		software requirements	
Net Data view		Start Reflection simulation	
select columns		SULTAN File	
Timing view		definition	43
Voltage view		open	
Screening commands		save	
SDF file		using	
description	61	Supply Nets	13
filename		edit	53
output		specifications	
Select nets to analyze		system	
Set Aggressor Net		requirements	5
Set Victim Net			
Signal Integrity		System messages	109
Device library	121	-Т-	
Device searching / handling		Take Over	
entry window		command	<b>/</b> 0
Getting started		Termination Advisor	49
		commands	60
Help topics	119	COMMINATIOS	69

introduction to		
Parallel R to GND		
Parallel R's to VCC and GND		
Serial R		
termination methods		
tutorial examples	29	
-U-		
Units and default values	173	
Units representation		
user manual		
organization	1	
-W-		
Wave Analyzer	77	
Analyze Baseline		
Analyze Cartes		
Analyze commands		
Analyze Fall time	85	
Analyze FFT		
Analyze Maximum	86	
Analyze menu	83	
Analyze Minimum	85	
Analyze Rise time	85	
Analyze Topline	86	
Cartesian coordiantes display	83	
clear measurement area	28, 82	
coordinate system		
copying wave to the clipboard	81	
Edit commands	81	
edit copy	81	
edit delete		
edit delete all waves	82	
Fdit menu	81	

	edit redraw	.82
	edit rescale	
	file exit	.81
	File menu	
	file open	.78
	file page setup	.80
	file print	
	file save	
	file save as	
	frequency domain view	
	Help commands	
	Help menu	
	Help topics	
	introduction to	
	Measurement area	.87
	measurement display	
	opening a wave file	
	Options commands	
	Options display	
	Options menu	
	Options wave	
	origin	
	print the display	.32
	printer setup	
	save file name	
	saving waves in a file	.78
	wave names	
	X-axis	.89
	Y-axis	
	zoom-in27,	
	zoom-out	
٧	Vave save file	